See MissingMenuGen homepage for more info, guides & updates http://homepage.mac.com/rnc

QUICK START

1) Select the "Type" of disk to build.

2) Press "Add", load in order, all the mpeg tracks you plan to use.

3) Select the a track in the window, click the "Previous" popup button.

Select the track to goto if the Previous button is pressed on the player.

Repeat for "Next" and "Return", the "Timeout" is where it will go after it

finishes playing the current track. If a entry is left blank, it will be set to END OF DISK.

4) "Set as Menu" will add Select by Number capability to that track. This is typicaly used on a short clip or mpeg still image as a

selection page.

Remember buttons will match sequeince order, and always start a 0.

A disk can have multiple menus and/or all tracks can have this feature.

Note: a still image must be a menu item, motion mpegs may be either menu or normal.

5) Number of times track will "Loop" before going to "Wait", useful for menu.

If the value is 0, track will be looped indefinitely.

6) Jump-Timing will go to button selection "Immediately" (recommended) or

"Delayed" till track has finished playing.

7) "Wait" is seconds after track has finished playing and looping before going to Timeout.

A value of -1 will pause indefinitely till Previous, Next, Return, or a Number button is pressed.

- 8) "Update" can be press at any time to store the settings.
- 9) "Remove" the selected track from the list.
- 10) "GenMenu" to build and save the XML file.

ADVANCED SETTINGS

11) Set the name of the "AlbumID", used by computer, may not be seen by stand alone player

12) Set the name of the "VolumeID", used by computer, may not be seen by stand alone player

13) Set the "Volume #", player may prompt, you for next disk in set.

14) Set "Chapters" entrypoints to scan forward to, default first point is at 0.00 from start.

Entrypoints will not be added to tracks tagged as "Menu".

Caution: total minutes must be equal to or less than the shortest track length.

15) "Options" are "update scan offsets" and "track pregapvalue=152"

These are required for some players to respond correctly to video disk.

Note: Not allowed in VCD and will be disabled if VCD is selected.

NOTE: Some additional features have been left out, for simplicity. Features can be added by popular demand.