

# Easy Macro Documentation

Easy Macro is a shareware program from Wintronix, Inc. Use beyond a ten day evaluation period without registering the program is illegal. This program can be distributed freely if all of the original files are included in the .ZIP file.

Easy Macro is a simple keystroke record and playback program. It is designed to be simple and unobtrusive. Often times a keystroke sequence needs to be repeated several times. Microsoft's Recorder will work, but it is usually not worth the effort to switch from your application, run it, select a playback key combination, record it, switch again from your application, and then terminate the recording. With Easy Macro running, you can hit a Start/Stop key, do your keystroke sequence, then hit the Start/Stop key again. Once you have done this you can playback the keystroke sequence merely by hitting the playback key. It can be used while you are using any Windows program. You do not have to switch away from your application. It patiently and silently monitors your keystrokes for the Start/Stop key. When it finds that key, it starts recording until you hit that same key again. Then it monitors for the playback key, springing into action by playing back your keystrokes, when it finds it.

To work properly EMLIB.DLL must be in the same directory as EM.EXE or your Windows directory, or in your path.

The unregistered version of the program will stop and ask for a confirmation of the playback 10% of the time. Additionally the unregistered version will not allow hiding of the icon.

To have the program readily available, edit your WIN.INI file. Add EM.EXE to the end of the line that has 'load ='. Make sure that EM.EXE is in the path or add the full path name for EM.EXE to the load line of your WIN.INI. An alternate method is to put EM.EXE in your Startup Group.

The default keys for Easy Macro are F7 and F8. To change the default keys, double click on the Easy Macro icon. You will be presented with your key choices. Choose your desired key combinations for the Start/Stop key and the Playback key. When you register the program, the hide icon will become functional.

To register the program, print a copy of REGISTER.WRI. Fill out the form, enclose a check drawn on a US bank and send to Wintronix.

Company names and products are trademarks, and registered trademarks of their respective owners.

WINTRONIX INC. SPECIFICALLY DISCLAIMS ALL WARRANTIES, EXPRESS OR IMPLIED. INCLUDING BUT NOT LIMITED TO, ANY IMPLIED WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

In no event will Wintronix, Inc.'s liability for any damages to you or any other person ever exceed the registration cost paid to license the program, regardless of any form of the claim.