NAME

frm,nfrm – list from and subject of selected messages in mailbox or folder

SYNOPSIS

frm [**–hnQqStv**] [**–s** *status*] [folder | username] ...
nfrm [**–hnQqStv**] [**–s** *status*] [folder | username] ...

DESCRIPTION

Frm outputs one line per message of the form:

from [subject]

where *from* is the name of the person the message is from, and *subject* is the subject of the message, if present. If the message is from you, the *from* portion will read ‘‘To user’’, where ‘user’ is the user the message was sent to. This happens when you receive a copy of a letter you sent.

If a folder is specified, the program reads that folder rather than the default mailbox. If the argument is a username then *frm* looks in that user’s mailbox, provided you have permission to read it.

A folder can be specified with the same notation as when invoking the **Elm** mailer (e.g., =folder).

Frm invoked as *nfrm* is identical to invoking ‘‘frm -s new’’.

OPTIONS

The *frm* program has the following options:

–h Print a brief help message summarizing the options.

–n Number the messages using the same numbering scheme that, for example, *readmsg* will understand.

–Q Very quiet mode. Only error messages are produced. This option is useful in shell scripts, where only the success or failure of the program is important, and output is not desired.

–q Quiet mode. Output only a one-line summary for each mailbox or folder specified.

–S Summarize the number of messages by message status in each mailbox or folder. If you want just a summary line, use this in conjunction with the **–q** option.

–s *status*
Only display headers from messages with the given status. ‘status’ is one of "new", "unread", "old" (same as "unread"), or "read". The **–s** option can be specified multiple times to print header information from, for example, only new and unread messages. It is sufficient to specify only the first letter of the status.

–t Tidy mode. If the *from* field is long enough to displace the subject field from its natural start column, move the subject down onto the next line.

–v Verbose mode. Print a descriptive header before listing the contents of each mailbox or folder.

EXIT STATUS

Frm returns a zero status ("true") if messages matching ‘status’ are present. *Frm* returns 1 if no messages matching ‘status’ are present, but there are some messages, returns 2 if there are no messages at all, or returns 3 if an error occurred. If multiple mailboxes or folders are specified, the exit status only applies to the last one examined. This can be used in scripts to determine what kind of mail a user has.

EXAMPLES

Some example uses:

$ **frm**

will display header information from all the messages in your mailbox, or ‘‘You have no mail.’’ if there are no messages in your incoming mailbox.

$ **frm -s new**

will display header information from all new messages in your mailbox, or ‘‘You have no new mail.’’ Note the slightly different diagnostic.

$ **frm -s new -s unread guest**

assuming you have the proper file permissions to read guest’s mail, will print out header information from all new and unread messages in guest’s incoming mailbox. If there are no messages, *frm* will print ‘‘guest has no mail.’’

$ **frm -q -S**

will print only a one line summary of how many read, unread, and read messages are in your incoming mailbox. For example, ‘‘You have 2 new messages, 3 unread messages, 23 read messages.’’

AUTHOR

Elm Development Group

SEE ALSO

readmsg(1L), elm(1L), mail(1), mailx(1)

BUG REPORTS TO

Syd Weinstein elm@DSI.COM (dsinc!elm)

COPYRIGHTS

©Copyright 1988-1992 by The USENET Community Trust
Derived from Elm 2.0, © Copyright 1986, 1987 by Dave Taylor