COMPUSERVE'S CSIR-Net Connect Note: These screens may not appear correctly on the Palm Pilot.
CompuServe's relationship with the CSIR network provides for asynchronous dial-up access from South Africa to hosts on CompuServe.
Dial CSIR-Net's node in South Africa and log on according to the appropriate instructions below. (If you dial CSIR-Net outside of the designated city you will incur normal long distance charges for the duration of the call, billed by your Telkom company on your telephone bill).
ACCESS INSTRUCTIONS: To connect to CompuServe through CSIR-Net, dial one of the local access numbers listed above and follow these logon instructions: 1. Establish a phone connection by dialing the your local CSIR-Net access number listed above.
2. Your screen will show: CONNECT 2400 or the appropriate baud rate at which you have connected.
Wait 5 seconds and type: X.28 where stands for carriage return.
3. Your screen will show: OOOOO O O O OO O O O OOO OO OO O O O O O O O O O O O O O OOOO O OO O O O O O O O O O O O O O O O O O OO O O O OOO O O O ---------- EASY ACCESS AFRIKAANS : SLEUTEL NUI IN.
ENGLISH : ENTER NUI FOR SERVICES.
ISIXHOSA : FAKA UNUI UKUFUMANA UNCEDO.
ISIZULU : NGENISA UNUI UKUTHOLA USIZO.
SEPEDI : TSENYA NUI GO HUMANA DITIRELO.
SESOTHO : KENYA NUI HO FUMANA DITSHEBEDISO.
---------- NUI?
4. At this prompt, you type: 901040OZ3U 5. Your screen will show: OOOOO O O O OO O O O OOO OO OO O O O O O O O O O O O O O OOOO O OO O O O O O O O O O O O O O O O O O O O O OO O O O OOO O O O MAIN INDEX ---------- EASY ACCESS * A .. TRIPLE-X * B .. BELTEL * C .. VIDEOTEX GATEWAYS * D .. DIRECTORY SERVICES * E .. MESSAGE TRANSFER SERVICES * F .. INTERPERSONAL MESSAGE SERVICE * G .. TELEX * H .. HELP * X .. CHANGE LANGUAGE * Y .. CHANGE TERMINAL TYPE * Z .. DISCONNECT * = ACCESSIBLE SERVICES ----------o---------- VT100 SELECT ?
6. At this prompt, you type: A 7. Your screen will show: ********** * CALL FORMAT: * * * * C (Gss)(,)(R)(-)xxxx * * C .yyyyzzzz * * * * where: * * ss = CUG index (00-99) * * R = reverse charge request * * xxxx = DTE address * * yyyy = nat. telephone area code * * zzzz = dest. telephone number * * * * Examples: * * C G02,R-19901234 * * C G22-19901234 * * C.012446387 * ********** PRESS 'ENTER' 3 TIMES FOR MAIN INDEX.
* 8. At this prompt, you type: C 10634679 9. You will then be connected to the CompuServe Host and receive a User ID prompt. Enter your CompuServe Information Service User ID and logon as usual.
User ID: