

# Documentation Corrections and Additions

## *HiJaak PRO 4.0 User Guide*

### Introduction

**Page 3:** Under the raster column of the table of supported formats, NIF—Navy Image File Format should be listed as source only. Under the vector column, add GCA—GOCA. Under the 3D column, add CGM Metafile (source only): HiJaak PRO can open and save 2D CGM files and it can open 3D CGM files. Note that if you open a 3D CGM file, modify it and try to save as CGM, HiJaak PRO will flatten the file and save as 2D CGM.

### Chapter 3: Managing and Thumbnailing Images

**Page 34:** Second paragraph: Add, "When the traffic light icon in the task tray is blue, the active catalog is read-only."

**Page 52:** Step 2 second paragraph: Replace the first sentence with, "Click the read only column beside the name of the catalog that you want to mark read only."

### Chapter 5: Changing the View

**Page 75:** Tip: 3D viewpoint, rendering and perspective changes cannot be reversed using Edit\Undo or the Esc key.

**Page 87** Step 3, last sentence: "One click on any button changes the angle of the viewpoint by 10 degrees." It should say "5 degrees."

**Page 89:** Wireframe: replace first sentence with "...displays the image with color, but no shading or light." The manual says that no color will display.

### Chapter 6: Editing and Enhancing Images

**Page 98:** Note: The Properties dialog box does not have a separate Class area. Whether the active image is Raster, Vector, Metafile or 3D is indicated in the Type area of this dialog box.

**Page 101:** There is an additional option in the Trace Options dialog box: View. You can select whether you want the traced image to replace the original, or display in a new window in addition to the original. To display the traced image in a new window, select Create New Image in the View area; this is the default setting. To replace the existing image, select Replace Existing Image in the View area.

**Page 103:** Step 10, 3rd paragraph. By default, HiJaak PRO takes the 120x120 pixels in the top-left corner of the image for the sample, not the center of the image.

### Chapter 9: Importing and Exporting Images

**Page 141:** First paragraph: "Once the graphics file is *linked* or embedded, you can double click the image and use HiJaak's menus from directly within the application." This in-place visual editing is available only if you embed the object, not if you link it. If you double click a linked image, HiJaak PRO will start and display the linked image for editing.

**Page 145:** To Edit a Linked or Embedded Image: see the entry above.

### Chapter 10: Changing the HiJaak PRO Setup

**Page 155:** Reduction Method bullet: replace the current description with, "controls the default color processing method used to convert images."

**Page 155:** Step 3: replace the first part of the step with, "To set the default color processing method HiJaak PRO uses to convert images...."