

Contents

The following Help Topics are available:

[Checking your Globalink Power Translator Pro Package](#)
[Installing Globalink Power Translator Pro](#)
[Installing Multiple Languages](#)
[Information for Network Administrators](#)
[Registering Globalink Power Translator Pro](#)
[Uninstalling Globalink Power Translator Pro](#)
[Viewing the Read Me File](#)

For Help on Help, Press F1

Checking your Globalink Power Translator Pro Package

Your Globalink Power Translator Pro package should contain the following items:

- The Globalink Power Translator Pro program CD
- User's Guide
- Registration Card

If an item is missing, contact the establishment from which you purchased Globalink Power Translator Pro.

Installing Globalink Power Translator Pro

To install Globalink Power Translator Pro, follow these steps:

- Insert the Installation CD into your CD ROM drive.
- Select Run from the Windows '95 Start menu. The Run dialog box will appear.
- In the Open text field, type D:\INSTALL (substitute the correct letter of your CD ROM drive if it isn't D). Click on OK.

Follow the instructions that appear on the screen to complete the installation. Installation options are described below.

Dictionary Options

If you are installing and using Globalink Power Translator Pro on a single machine, select the Standalone Dictionary Option. This will copy the Globalink Power Translator Pro dictionary files to the same directory as the program files (C:\PTWIN63).

If you are installing Globalink Power Translator Pro for use with a network, and the dictionary files are being stored on a network drive, select the Shared Dictionary Option. This will give you an opportunity to specify the drive and directory of the shared dictionaries. For complete network installation instructions, see the section titled [Information for Network Administrators](#)

Word Processor Support

You can now translate documents directly within Microsoft Word for Windows Version 6.0 or 7.0, or Corel WordPerfect 6.0 or 7 for Windows. During installation of Globalink Power Translator Pro, you will be given the option to install support for Microsoft Word and/or Corel WordPerfect for Windows. If this option is selected, the appropriate files will be copied into your word processor's directory. The next time you start Microsoft Word for Windows 6.0 or 7.0 or Corel WordPerfect for Windows 6.0 or 7, the option TRANSLATE will appear on your menu bar. For more information on translating files from within Word or WordPerfect, see the appendix titled "Word Processor Support." in the Globalink Power Translator Pro User's Guide.

Installing Multiple Languages

If you install additional Globalink Power Translator Pro language pairs, it is recommended that you install them to the same directory as your initial Globalink Power Translator Pro installation (C:\PTWIN63). This will eliminate the duplication of program files and reduce the disk space required for multiple installations.

Once you have installed the additional programs, those language pairs will appear among your Source/Target Language Pair choices for projects, dictionaries, and inflections.

Information for Network Administrators

Globalink Power Translator Pro can be installed and configured for use on a network. This allows users to share common lexicon files (dictionaries) and only have the product executables and related files installed to their local drives. To install the program for network use, you must first install to the server and then to local machines.

Server Installation:

To install Globalink Power Translator Pro on a machine acting as a server do the following:

1. Place the installation CD in the CD ROM drive.
2. Select Run from the Windows '95 Start menu.
3. Type D:\Setup in the Open text box, and click on OK to start the installation (substitute the correct drive letter for your CD ROM drive if it is not D).
4. Enter the correct registration information and serial number (the serial number can be found inside the front cover of the manual and on the registration card) and click on OK to continue the installation.
5. Indicate the network location to which you wish to install the program. This should be the drive from which the lexicon files will be shared.
6. Make sure that Local is selected as the Dictionary Option. Do NOT select Microsoft Word or WordPerfect support unless you want files copied to those word processor's directories on the Server.
7. Click on OK to continue the installation. Once you have completed the server portion of the installation, you can install to user's local drives.

Note: Local installation must conform to your Globalink Power Translator Pro license agreement.

Workstation Installation:

To install Globalink Power Translator Pro on a workstation machine connected to the above mentioned server do the following:

1. Follow steps one through four of the Server Installation instructions above.
2. Indicate the local directory to which you wish to install the program files.
3. Click on Shared as the Dictionary Option in the Standard Installation dialog box, and click OK to continue.
4. Locate the drive and directory of the files you installed in the Server Installation. Click on OK to accept that location for the shared dictionaries.
5. Follow the prompts to complete the installation.

Once you have completed the installation, you must run the Dictionary Setup program on each of the workstation machines on which you have installed Globalink Power Translator Pro. Use the Windows Explorer to view the files in the Globalink Power Translator Pro directory. Double click on the DSETUP.EXE file to start the dictionary setup.

In the *Location of Globalink Power Translator Pro* text box, type the full pathway of the local directory where you installed Globalink Power Translator Pro (not the server installation), or use the Browse button to locate the file BARCSRV.EXE (this should be on the local machine, in the PTWIN63 directory).

In the Location for Shared Dictionaries text box, type the full pathway of the shared directory where you installed Globalink Power Translator Pro in the Server Installation, or use the browse button to locate any of the LEX or CDS files from that installation. Click on OK to complete the Dictionary Setup.

Globalink Power Translator Pro is now configured for network use. Please note that changes made to the general dictionaries or any subject-specific dictionaries will affect all users of the program.

Viewing the Read Me File

After you have installed Globalink Power Translator Pro, you will be given an opportunity to view the Read Me file. This file contains up-to-date information about Globalink Power Translator Pro that was not available when this user's guide was printed.

If you want to view the Read Me file at a later date, double-click on the README.HLP file in the directory where you have installed Globalink Power Translator Pro.

Registering Globalink Power Translator Pro

Please remember to register your Globalink Power Translator Pro. Registering entitles you to technical support, upgrade notifications, and special offers on other products.

If you complete the registration card after using the program, please fill in the comments portion of the card. We appreciate your ideas and opinions.

Uninstalling Globalink Power Translator Pro

The Globalink Power Translator Pro Uninstaller will remove selected products or the entire Globalink Power Translator Pro product from your machine. To uninstall Globalink Power Translator Pro, follow these steps:

- Start the Uninstaller by double clicking on the Uninstaller file, UNINSTAL.EXE, using the Windows Explorer or File Manager. The Uninstall window will appear.
- Select the item(s) you want removed and the uninstaller will remove the appropriate files from you hard drive and delete the appropriate entries from the registry.

If the remove all options is selected or if the last remaining product is being removed, the uninstaller will remove the program group and delete the directory.

