

Sheet1

FIELD_NAME	FIELD_TYPE	FIELD_LENGTH	FIELD_FORMAT	TITLE	PROG
FIELD_NAME	C	170		TITLE,C,30	PROGF
sys_no	C	15	sys_no	System Number	HSIM
ser_no	C	15	ser_no	Serial Number	HSIM
reg_no	C	15	PADR(reg_no,19)	Registration Number	HSIM
prodname	C	25	prodname	Product Name	HSIM
desc	C	45	desc	Device Description	HSIM
dtype	C	3	PADR(dtype,11)	Device Type	HSIM
dt purch	D	8	PADR(TRANS(dt purch,'@D'),14)	Date Purchased	HSIM
wexpdt	D	8	PADR(TRANS(wexpdt,'@D'),24)	Warranty Expiration Date	HSIM
support	C	15	support	Vendor Support	HSIM
scost	N	7	PADL(TRANS(scost,'#####.##'),15)	Purchased Price	HSIM
vendor	C	15	PADR(vendor,17)	Hardware Supplier	HSIM
mfg	C	15	mfg	Manufacture	HSIM
h type	C	3	PADR(h type,13)	Hardware Type	HSIM
tdesc	C	40	tdesc	Hardware Type Description	HSIM
pcno	C	3	PADR(pcno,10)	Printer ID	HSIM
prnname	C	30	prnname	Printer Name	HSIM
prnintern	N	1	TRANS(prnintern,'99999999999999999999')	Network Printer Number	HSIM
prnreset	C	50	prnreset	Printer Reset Sequence	HSIM
prnlev1	C	50	prnlev1	Printer Level 1	HSIM
prnw1	N	3	TRANS(prnw1,'999999999999')	Printer Width	HSIM
prnlen1	N	3	TRANS(prnlen1,'999999999999999999')	Printer Page Length	HSIM
prnlev2	C	50	prnlev2	Printer Level 2	HSIM
prnw2	N	3	TRANS(prnw2,'999999999999')	Printer Width	HSIM
prnlen2	N	3	TRANS(prnlen2,'999999999999999999')	Printer Page Length	HSIM
prnlev3	C	50	prnlev3	Printer Level 3	HSIM
prnw3	N	3	TRANS(prnw3,'999999999999')	Printer Width	HSIM
prnlen3	N	3	TRANS(prnlen3,'999999999999999999')	Printer Page Length	HSIM
outfile	C	50	outfile	Output file name	HSIM
browse	L	1	PADR(TRANS(browse,'L'),6)	Browse	HSIM
sys_no	C	15	sys_no	System Number	HSIM
reg_no	C	15	PADR(reg_no,19)	Registration Number	HSIM
prodname	C	25	prodname	Product Name	HSIM
desc	C	45	desc	Product Description	HSIM
ptype	C	3	PADR(ptype,12)	Program Type	HSIM
swtype	C	1	PADR(swtype,13)	Software Type	HSIM
pversion	C	6	PADR(pversion,15)	Program Version	HSIM
dt purch	D	8	PADR(TRANS(dt purch,'@D'),14)	Date Purchased	HSIM
wexpdt	D	8	PADR(TRANS(wexpdt,'@D'),24)	Warranty Expiration Date	HSIM
support	C	15	support	Vendor Support	HSIM
regflag	C	1	PADR(regflag,17)	Registration Flag	HSIM
scost	N	7	PADL(TRANS(scost,'#####.##'),15)	Purchased Price	HSIM
dsksize	C	5	PADR(dsksize,9)	Disk Size	HSIM
vendor	C	15	vendor	Software Vendor	HSIM
sys_no	C	15	sys_no	System Number	HSIM
sys_ser	C	15	sys_ser	Serial Number	HSIM
desc	C	45	desc	Description	HSIM
name	C	30	name	Name	HSIM
address1	C	40	address1	Address Line 1	HSIM

Sheet1

address2	C	40 address2	Address Line 2	HSIM
city	C	30 city	City	HSIM
state	C	2 PADR(state,5)	State	HSIM
zip	C	10 zip	ZIP Code	HSIM
priphone	N	14 TRANS(priphone,'(999) 999-9999')	Primary Phone	HSIM
priext	N	4 TRANS(priext,'9999999999999999')	Primary Extension	HSIM
secphone	N	14 PADL(TRANS(secphone,'(999) 999-9999'),15)	Secondary Phone	HSIM
secext	N	4 TRANS(secext,'9999999999999999')	Secondary Extension	HSIM
mtype	C	3 PADR(mtype,13)	Software Type	HSIM
tdesc	C	40 tdesc	Software Type Description	HSIM
vendor	C	15 vendor	Vendor Name	HSIM
vendname	C	35 vendname	Full name of Vendor	HSIM
vaddr1	C	30 vaddr1	Address Line 1	HSIM
vaddr2	C	30 vaddr2	Address line 2	HSIM
vcity	C	25 vcity	City	HSIM
vstate	C	2 PADR(vstate,5)	State	HSIM
vzip	C	10 vzip	ZIP Code	HSIM
vphone	N	14 TRANS(vphone,'(####) ###-####')	Phone Number	HSIM

Sheet1

FILENAMFIEPHFFIELD	EXP,C,30	FIELDMASK,C,30
hardwre	0 15_FIELD->sys_no	
hardwre	0 15_FIELD->ser_no	
hardwre	0 19_FIELD->reg_no	
hardwre	0 25_FIELD->prodname	
hardwre	0 45_FIELD->desc	
hardwre	0 11_FIELD->dtype	
hardwre	0 14_FIELD->dtpurch	@D
hardwre	0 24_FIELD->wexpdt	@D
hardwre	0 15_FIELD->support	
hardwre	2 15_FIELD->scost	#####.##
hardwre	0 17_FIELD->vendor	
hardwre	0 15_FIELD->mfgr	
htype	0 13_FIELD->htype	
htype	0 40_FIELD->tdesc	
prnlist	0 10_FIELD->pcno	
prnlist	0 30_FIELD->prnname	
prnlist	0 22_FIELD->prntern	99999999999999999999
prnlist	0 50_FIELD->prnreset	
prnlist	0 50_FIELD->prnlev1	
prnlist	0 13_FIELD->prnw1	99999999999999
prnlist	0 19_FIELD->prnlen1	999999999999999999
prnlist	0 50_FIELD->prnlev2	
prnlist	0 13_FIELD->prnw2	99999999999999
prnlist	0 19_FIELD->prnlen2	999999999999999999
prnlist	0 50_FIELD->prnlev3	
prnlist	0 13_FIELD->prnw3	99999999999999
prnlist	0 19_FIELD->prnlen3	999999999999999999
prnlist	0 50_FIELD->outfile	
prnlist	0 6_FIELD->browse	
softwre	0 15_FIELD->sys_no	
softwre	0 19_FIELD->reg_no	
softwre	0 25_FIELD->prodname	
softwre	0 45_FIELD->desc	
softwre	0 12_FIELD->ptype	
softwre	0 13_FIELD->swtype	
softwre	0 15_FIELD->pversion	
softwre	0 14_FIELD->dtpurch	@D
softwre	0 24_FIELD->wexpdt	@D
softwre	0 15_FIELD->support	
softwre	0 17_FIELD->regflag	
softwre	2 15_FIELD->scost	#####.##
softwre	0 9_FIELD->dsksize	
softwre	0 15_FIELD->vendor	
system	0 15_FIELD->sys_no	
system	0 15_FIELD->sys_ser	
system	0 45_FIELD->desc	
system	0 30_FIELD->name	
system	0 40_FIELD->address1	

Sheet1

system	0	40_FIELD->address2	
system	0	30_FIELD->city	
system	0	5_FIELD->state	
system	0	10_FIELD->zip	
system	0	14_FIELD->priphone	(999) 999-9999
system	0	17_FIELD->priext	9999999999999999
system	0	15_FIELD->secphone	(999) 999-9999
system	0	19_FIELD->secext	9999999999999999
types	0	13_FIELD->mtype	
types	0	40_FIELD->tdesc	
vendor	0	15_FIELD->vendor	
vendor	0	35_FIELD->vendname	
vendor	0	30_FIELD->vaddr1	
vendor	0	30_FIELD->vaddr2	
vendor	0	25_FIELD->vcity	
vendor	0	5_FIELD->vstate	
vendor	0	10_FIELD->vzip	
vendor	0	14_FIELD->vphone	(###) ###-####