

Program Switcher v3.2.1

Copyright ©1995 by Michael F. Kamprath

<mailto:kamprath@kagi.com>

<http://www.leonardo.net/kamprath/clairaware.html>

Program Switcher is a useful control that allows you to switch between the running programs on your System 7 or greater Mac via simple two-key keystroke. This feature was inspired by the same Windows functionality, but I have improved on it and made an unique and fully configurable control panel which makes switching applications on the Macintosh as simple as pressing some keys.

Instructions

Program Switcher requires System 7 or greater. To install it, just drag the control panel to your system folder icon and "drop." Restart your computer. To use, hold down the activating key (by default, the option key) and then tap the switching key (tab key). A window will appear displaying the next program running on your Macintosh. While still holding the activating key (option key) down, tapping the switching key (tab key) again shows the program after that. When the program you want to switch to is currently being displayed by Program Switcher, let go of the activating key (option key) and that program will be brought to the front. During the switching process, you may see the previous application displayed by tapping the shift key while still holding down the activating key. If you would like to cancel out of the switching process and immediately return to the original application you were in, release the activating key while still holding down the switching key.

To customize your settings, open the Program Switcher control panel itself. You will see that there are several options that you may use to customize Program Switcher's performance with. They are:

Control Keys: Under this option are two pop-up menus, one titled "Activator" and the other "Switcher." With these menus, you can set the activating and switching keys (respectively).

Hide Other Applications: Checking this check box causes Program Switcher to hide all other applications after an application switch has been performed. This is only active if Program Switcher performs the switch.

Exclude Certain Applications: Checking this check box allows Program Switcher to exclude certain applications from being displayed during the switching process. You must specify the applications you wish Program Switcher to exclude. This option is useful if you have some applications that always run but you may not want to switch to that often (for example, Darkside of the Mac). Leave this option unchecked to make Program Switcher display all running applications always.

Set Applications...: Clicking this button brings up a dialog in which you may specify the applications for Program Switcher to exclude if the Exclude Certain Applications option is checked.

Set Display Window Attributes...: Clicking this button brings up a dialog in which you may customize the appearance of the window that Program Switcher displays when the switching process is taking place. You may set the font and font size that Program Switcher uses to write the application name with, the specific type of window that Program Switcher displays, the background color of the window, whether Program Switcher displays the applications' icons or not, and the size of the application icon cache that Program Switcher uses. The application icon cache saves an application's icon in RAM in order to speed up the display of the switching window. This cache requires about 3K of RAM for each application icon. The required RAM is allocated in your system software's memory block. If your RAM situation is tight, just just off this cache and all of it's memory will be freed. When the cache is shut off, Program Switcher will get an application's icon from the hard drive each time it is displayed.

I have paid my shareware fee!: Check this checkbox only after you have paid your shareware fee.

Program Switcher always displays the last program that you were working in first when starting the switching process. If that application is no longer running, then Program Switcher displays the first application in the System's applications menu.

Shareware Information

Program Switcher is not free. If you use Program Switcher for more than one week, you must pay the US\$10 registration fee. You may do this by using the enclosed Register application. Be sure to follow Register's instructions carefully. If you are using this program to pay by check, be sure to make your checks out to "Kagi Shareware." Also, please be sure to send your payments to the address listed on the form that the Register program produces -- please do not send payments to be processed by Kagi Shareware directly to me.

If you are on CompuServe, you can register Program Switcher online. Type GO SWREG for more information. Program Switcher's registration code is 6209. CompuServe only allows single user license registrations.

Contacting the Author

You may contact me through e-mail at:

<mailto:kamprath@kagi.com>

Or by snail mail at the address above.

WARRANTY

USE OF THIS PRODUCT, PROGRAM SWITCHER, IMPLIES THAT YOU WILL HOLD MICHAEL F. KAMPRATH HARMLESS TO ANY DAMAGES CAUSED BY THE PERFORMANCE OF THIS PRODUCT. YOU ALSO AGREE THAT MICHAEL F.

KAMPRATH CAN NOT BE HELD LIABLE FOR ANY OTHER DAMAGES YOU MAY INCUR BY THE USE OF THIS PRODUCT. MICHAEL F. KAMPRATH PROVIDES NO WARRANTY, WHETHER EXPRESSED OR IMPLIED, OF THIS PRODUCT, INCLUDING IT'S MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT.

"Windows" is a trademark of that company run by Bill Gates.