

Installing Green Screen Savers

"Jumping Frog Green Saver" and "Jumping Cricket Green Saver" are Windows 95 & Windows NT applications which display an animated picture (with optional sound) on your screen for a user selected period of time. The screen will then go completely blank so that Energy Star monitors can enter a power saving mode. This application is targeted for Windows NT ver. 3.51 and Windows 95; it will not work properly on 16-bit Windows 3.x.

To install the Green Screen Savers, extract the files in the archive file to a floppy disk or into a temporary subdirectory (folder) of your choice. Then execute the file INSTALL.BAT from within that subdirectory. You may also copy the files directly into the appropriate Windows\SYSTEM directory using the format below (%windir% is the root Windows directory on your system).

Manual Windows NT installation:

```
copy FROGSAV.SCR %windir%\SYSTEM32\FrogSav.scr
copy CRICKSAV.SCR %windir%\SYSTEM32\CrickSav.scr
copy GREENSAV.WRI %windir%
```

Manual Windows 95 installation:

```
copy FROGSAV.SCR %windir%\SYSTEM\Jumping Frog Green Saver.scr"
copy CRICKSAV.SCR %windir%\SYSTEM\Jumping Cricket Green Saver.scr"
copy GREENSAV.WRI %windir%
```

Setup options:

When the setup option is selected from control panel for these screen savers, one of the options is to register the program. Once the program has been registered, this selection will still appear, but will no longer do anything. The registration dialog will request a Product ID which may be obtained by following the instructions on the last page of this document. This program does not contain a "time bomb" to limit its unregistered usage, but you will have to register the program to remove the reminder to register which is displayed when the screen saver runs. You may use the last page of this file as an order form to obtain the Product ID code needed to complete the registration process. You may also register this program via Compuserve (GO SWREG, Registration ID: 7866)

The default values for the other setup options will probably work for most users, but several parameters are configurable by the user.

1. Jump Speed: (default = 25) [1 = fast , 100 = slow motion] any integer value may be entered, but
values between 1 and 100 will probably work for most systems.
2. Jump Length (default = 5) [1 = short, 10 = long] any integer value may be entered, but values
between 1 and 10 will probably work for most systems.
3. Initial X position (default = 0) The initial X-axis screen coordinate of the jumping critter.
4. Initial Y position (default = 0) The initial Y-axis screen coordinate of the jumping critter.
5. Delay until black (default = 200) The number of time the critter will jump before the screen
goes black. (Set to 0 to disable this feature).

You may pass this (unregistered) program along to your friends and associates who have power saving monitors (or who like crickets or frogs). Please distribute the original archive file rather than the individual files contained therein. (The archive file is located in the REDIST subdirectory if you are installing from the floppy disk version). You may also post it to any BBS or on-line service. We only ask that if you continue to use this program on a regular, basis that you register it.

The files included in the archive are:

FROGSAV.SCR	The main executable file for "Jumping Frog Green Saver".
CRICKSAV.SCR	The main executable file for "Jumping Cricket Green Saver".
GREENSAV.WRI	This file.. Installation, troubleshooting and Registration information
INSTALL.BAT	Install program... Installs the screen savers to SYSTEM directory.
GREENSAV.TXT	Brief description of program

Digital Control Systems

P.O. Box 505

Hermitage, TN. 37076

(615) 889-6357 Fax: (615) 889-9595 Email: 73347.145@compuserve.com

Registration form for Green Screen Savers

Name: _____
Organization: _____
Address: _____
City: _____
State or Province: _____
Postal code: _____
Country: _____
Phone: _____ Fax: _____
Email: _____

Number of copies of GREENSAVER to register (\$10.00 each): _____
____ Check here if you wish to receive a copy of GREENSAVER on floppy disk.
The price per copy will be increased to \$15.00 to cover media and shipping.
Select desired disk format... 3.5" _____ or 5.25" _____

Call for site / organization license info if registering 10 or more copies.

Payment methods

____ Check here if paying by check or money order.
Payment should be in US funds for \$10.00 for each copy of GREENSAV which you wish to register. (\$10.00 for 1 copy, \$20.00 for 2 copies, \$ 30.00 for 3 copies, etc.)
Make the check or money order payable to: Digital Control Systems.

You may also register this program via Compuserve (GO SWREG, Registration ID: 7866)

We will also accept Visa or MasterCard.
____ Check here to charge to your Visa account.
____ Check here to charge to your MasterCard account.

Name (as it appears on card): _____
Card Number: _____ Exp date: _____

Signature: _____

If paying by credit card:
You may fax this form to (615) 889-9595.
You may send a copy of this file to our email address: 73347.145@compuserve.com.
You may also call us at: (615) 889-6357.

You may also use our Postal mailing address (required for check or money order):

Digital Control Systems
P.O. Box 505
Hermitage, TN. 37076