

ñshade TrackCursorInfo Object

The **TrackCursorInfo** Object provides properties/methods for tracking the position of the cursor in the report and for setting cursor icons for the specifies areas of the report. Cursor icon availability will vary depending on your development platform.

Properties

Application - Returns a reference to the Application Object this object is associated with. Read only.

DetailAreaCursor - Returns/Sets CRTrackCursor (see table below GroupAreaFieldCursor property) indicating what type of cursor to be displayed when the cursor is moved over the Details Area. Check your operating system documentation for a list of cursors available on your system. If you choose an unavailable cursor, the default (arrow) cursor will be uned. Read/Write.

DetailAreaFieldCursor - Returns/Sets CRTrackCursor (see table below GroupAreaFieldCursor property) indicating what type of cursor to be displayed when the cursor is moved over fields in the Details Area. Check your operating system documentation for a list of cursors available on your system. If you choose an unavailable cursor, the default (arrow) cursor will be uned. Read/Write.

GraphCursor - Returns/Sets CRTrackCursor (see table below GroupAreaFieldCursor property) indicating what type of cursor to be displayed when the cursor is moved over a graph. Check your operating system documentation for a list of cursors available on your system. If you choose an unavailable cursor, the default (arrow) cursor will be uned. Read/Write.

GroupAreaCursor - Returns/Sets CRTrackCursor (see table below GroupAreaFieldCursor property) indicating what type of cursor to be displayed when the cursor is moved over the Group Area. Check your operating system documentation for a list of cursors available on your system. If you choose an unavailable cursor, the default (arrow) cursor will be uned. Read/Write.

GroupAreaFieldCursor - Returns/Sets CRTrackCursor (see table below) indicating what type of cursor to be displayed when the cursor is moved over fields in the Group Area. Check your operating system documentation for a list of cursors available on your system. If you choose an unavailable cursor, the default (arrow) cursor will be uned. Read/Write.

crAppStartingCursor	12
crArrowCursor	1
crCrossCursor	2
crDefaultCursor	0
crHelpCursor	13
crIBeamCursor	3
crIconCursor	15
crMagnifyCursor	99
crNoCursor	10
crSizeAllCursor	5
crSizeCursor	14
crSizeNESWCursor	7
crSizeNSCursor	9
crSizeNWSECursor	6
crSizeWECursor	8
crUpArrowCursor	4
crWaitCursor	11

Parent - Reference to the Parent object PrintWindowOptions Object). Read only.

Report - Reference to Report Object. Read only.