

## Connection and Server Information

### EARTHLINK SUBSCRIBERS

Subscribers logging into EarthLink must use the following format in the **Username** field:

- **Username:** *username@earthlink.net*

The **POP** and **SMTP** Server settings are required in order to Send/Receive email through the EarthLink Servers.

- **POP Server:** pop.earthlink.net
- **SMTP Server:** smtp.earthlink.net

The **NNTP** (or **News**) Server setting is needed in order to gain access to EarthLink's News Server.

- **NNTP/News Server:** news.earthlink.net

Every EarthLink subscriber is provided with a FREE EarthLink webspace:

- **Webspace address:** *http://home.earthlink.net/~username*

The **FTP** and **Domain Server** settings are required to make changes to (or build) your webspace:

- **FTP Server:** ftp-www.earthlink.net (6mb webspace only)
- **FTP Domain Server:** ftp-dom.earthlink.net (Domain hosting only)

In order for members to establish a connection with EarthLink, any two of the three DNS numbers below must be entered in the Network settings.

- **DNS Servers:** 207.217.77.82  
207.217.120.83  
207.217.126.81

### MINDSPRING SUBSCRIBERS

Subscribers logging into MindSpring must use the following format in the **Username** field:

- **Username:** *username@mindspring.com*

The **POP** and **SMTP** Server settings are required in order to Send/Receive email through the MindSpring Servers.

- **POP Server:** pop.mindspring.com
- **SMTP Server:** smtp.mindspring.com

The **NNTP** (or **News**) Server setting is needed in order to gain access to MindSpring's News Server.

- **NNTP/News Server:** nntp.mindspring.com

Every EarthLink subscriber is provided with a FREE EarthLink webspace:

- **Webspace address:** *http://username.home.mindspring.com*

The **FTP** and **Domain Server** settings are required to make changes to (or build) your webspace:

- **FTP Server:** ftp.mindspring.com (6mb web space only)
- **FTP Domain Server:** ftp.business.earthlink.net (Domain hosting only)

In order for members to establish a connection with EarthLink, any two of the three DNS numbers below must be entered in the Network settings.

- **DNS Servers:** 207.69.188.187  
207.69.188.186  
207.69.188.185