



DataDirect ODBC NetWare SQL Driver

[Logon To NetWare SQL](#)

[NetWare SQL ODBC Setup](#)

[Copyright](#)

Copyright 1995 INTERSOLV Inc. All rights reserved. INTERSOLV is a registered trademark, and DataDirect is a trademark of INTERSOLV, Inc. Other company or product names mentioned herein may be trademarks or registered trademarks of their respective companies.

Configuring a NetWare SQL Data Source

Data Source Name: A string that identifies this NetWare SQL data source configuration in ODBC.INI. Examples include "Accounting" or "NetWare SQL-Serv1."

Description: An optional long description of a data source name. For example, "My Accounting Database" or "NetWare SQL on Server number 1."

Data Dictionary Path: The directory or path of the data dictionary files you want to access. Your ODBC application uses this path to connect to NetWare SQL and give you access to the data dictionary files in that directory. This may be the same as your Data Files Path.

Data Files Path: The directory or path of the data files you want to access. Your ODBC application uses this path to connect to NetWare SQL and give you access to the data files in that directory.

The following values are optional:

Default User Name: The default user name used to connect to your NetWare SQL database. This value is case-sensitive. Your ODBC application may override this value or you may override this value in the Logon dialog box or connection string. A user name is required only if security is enabled on your database.

Array Size: The number of bytes the driver uses for fetching multiple rows. Values can be 0 to 65536 bytes; the default is 4000. Larger values increase throughput by reducing the number of times the driver fetches data across the network. Smaller values increase response time, as there is less of a delay waiting for the server to transmit data.

Blank Escape: NetWare SQL lets you specify blanks as part of table or field names. The blank escape character is used to replace these blanks. The default blank escape character is a caret (^). Other values are tilde (~) and underscore (_).

Translate: Displays the Select Translator dialog box to allow you to perform a translation of your data from one character set to another. Choose the INTERSOLV OEM ANSI translator to translate your data from the IBM PC character set to the ANSI character set.

Logon to NetWare SQL

Data Files Path: Type the database name or the complete pathname of the directory containing your data files.

Data Dictionary Path: Type the database name or the complete pathname of the directory containing your data dictionary files.

User Name: If security has been enabled on your NetWare SQL database, type your user name.

Password: If security has been enabled on your NetWare SQL database, type your password.

