

What is MP3 CD Maker

Welcome to MP3 CD Maker Version 1.19

Do you want to make your own audio CDs that contain only your most favorite songs? You can do it now, just using MP3 CD Maker.

MP3 CD Maker is the coolest tool to burn your own audio CDs. It uses MP3 music files as audio sources. This means you can burn MP3 music files directly into normal audio CDs so that you can listen these cool musics in your ordinary audio CD players, H-Fis , even in cars!

MP3 CD Maker is also a MP3 decoder. You can use MP3 CD Maker to convert MP3 files into WAV files.

MP3 CD Maker is very small. The whole package is less than 600KB.

MP3 CD Maker is extremely easy to use. To record an audio CD simply click the "+" button to add MP3 files into the audio track list, then click "Rec" button to burn the CD! You can also arrange the audio track sequence. Double click the MP3 file you can listen to the music.

MP3 CD Maker support more than 360 popular CDR/RW drives, such as Yamaha series, HP CD-Writer+ 7100,7200,7500,8100,8200 , Ricoh MP6200S, MP7040A, Panasonic 7502,7582 ...

MP3 CD Maker burns audio CDs directly, it DOES NOT generate any tempory wav files. So the recording procedure is very fast, depending only on recorder speed and CPU speed.

MP3 CD Maker is a shareware. The unregistered version is limited to burn no more than **9 songs** on an audio CD. To get the full version, you have to register the software from the author. The registration fee is US\$29.95. To register MP3 CD Maker, simply click "**BuyNow**" button in the main window or visit my home page at

<http://www.zy2000.com>.

BTW: MP3 CD Maker does not generate "MP3 CDs" , it generates normal audio CDs. So you can only burn 74 minute songs (about 15 songs) on a CD .It can not let your normal CD player play over 100 songs on a CD.

MP3 CD Maker Version

Copy 1999(c) by Zhou Yi All rights reserved

Home Page: <http://www.zy2000.com>

Email: Support@zy2000.com

System requirement

Hardware requirement

- Pentium 100 PC or higher.
- 32 MB RAM space or more.
- 5 MB free hard disk space or more.
- CD Recorder
- Sound card (optional)

Software requirement

- Windows 95, Windows 98 or Windows NT 4.0 or higher

Quick Start

Now let's begin

STEP 1: Insert MP3 files

Click "+" sign to select mp3 files. you can select more than one file at a time by holding Ctrl key or Shift key while clicking the mouse button.

STEP 2: Play the MP3 songs (Optional, sound card needed)

Double click the MP3 song's name in the list to listen.

STEP 3: Adjust the MP3 song's list

1) Delete

Click the MP3 song's name you want to delete, then click the "-" sign.

2) Insert more songs

Click "+" button to insert more songs.

3) Adjust song's position in the list

Drag the song to the position you want and drop.

STEP 4: Record the song's to CDR

Insert a blank CDR into CDR/CDRW drive. When the drive's led shows "Ready", Click "Rec" button.

Select writing speed in the record dialog box.

If you just want to test the CDR drive, click "Test" Button.

If you are ready to record the CDR, click "Record" Button.

FAQ

What is MP3 CD Maker?

MP3 CD Maker is a very cool tool that can help you to make normal audio CDs from MP3 files. With MP3 CD Maker, you can choose up to 74 minutes of your favorite MP3 songs and burn them into a 74 minute audio CD so that you can listen to them in your ordinary CD players, even in your cars.

Does MP3 CD Maker burn more than 120 songs on a CD?

NO. MP3 CD Maker makes normal audio CDs, it uses MP3 files as sound source, but only burns 74 minute music on a CDR.

How to get the latest version of MP3 CD Maker?

Please visit our web site at <http://www.zy2000.com> to download the latest version of MP3 CD Maker. *All upgrades are free to registered users.*

I have got the registration code, how do I register?

Click the "Register" word on the lower right of MP3 CD Make's main user interface and enter your reg name and reg code in the dialog box.

Does MP3 CD Maker use a lot of hard disk space?

NO. Unlike other audio CD recording software, MP3 CD Maker burns MP3 files directly into audio CDs. It does not generate any temporary wav files.

Can I Convert MP3 files to WAV files?

Yes. MP3 CD Maker can convert MP3 files into WAV files. Point the mouse cursor to the mp3 file in the mp3 list, click the right mouse button, select 'export to wav' in the menu.

Does MP3 CD Maker support non-CD-quality MP3 files?

Yes. MP3 CD Maker not only supports 44.1KHz, Stereo CD quality MP3 files, but also supports other MP3 files such as 48KHz, 32KHz, 22KHz sample rate, stereo or mono MP3 files. MP3 CD Maker Version 1.16 and above have a sample-rate conversion feature.

What is "Normalizing" ?

"Normalizing" feature lets you ensure that all MP3s in a set have the same volume level.

Does MP3 CD Maker equalize the volume so that all the songs will have the same volume?

Yes. MP3 CD Maker has a "Normalizing" feature that lets you ensure that all MP3s in a set have the same volume level.

Does MP3 CD Maker support Disc-At-Once?

Yes. MP3 CD Maker works with disc-at-once mode.

Why the program shows "Can not send CUE sheet"?

The reason for this problem is that you have selected too many songs. Please reduce some songs in your song list and try again.

What if my cd recorder is not supported by MP3 CD Maker?

If MP3 CD Maker can not recognize your cd recorder, it will generate a file located at "C:\CDRLOG.TXT". Send this file to us via email and we will try to add a driver for this model as soon as possible.

Why my cdrw disc will not play in our home or car stereo system?

Not all players get along with all brands of CD-R/RW media. You need to find a combination of recorder, media, and player that get along.

Sometimes the CD player will have no problem playing the tracks, but will have a great deal of difficulty seeking between tracks or moving fast-forward. Using a different brand of media or a different CD player may produce better results.

Some media works better at 1x, 2x, or 4x than it does at other speeds. You may find that slowing down or speeding up the recorder helps.
We found "KODAK Gold ULTIMA" CD-R disc is very good for making CDs.

Why did my CD-R eject between the "test" and "write" passes?

The reason for this problem is that the recording speed is too high. You should try by lowering down the recording speed to 1x.

What recording speed can I reach?

The recording speed depends on the CPU speed because MP3 CD Maker does the MP3 decoding work and burning work simultaneously. Generally, you can use 4x recording speed if the CPU is faster than 233MHz.

I have entered the registration code, but I can still record only 9 songs, why?

Maybe you entered a wrong registration code.

You can solve this problem by removing the file "MP3CD.KEY" from MP3 CD Maker's working directory. Generally, MP3 CD Maker is installed to "C:\Program Files\MP3CD\".

After you remove the file "MP3CD.KEY", re-launch MP3 CD Maker, and insert the registration code again.

Do I have to pay for the upgrades?

NO. All upgrades are free to registered MP3 CD Maker users.

Can I buy MP3 CD Maker if I do not have a credit card?

Easy... Just send a check or money order for \$29.95 to:

Qwerks.com Inc
1648 West Willow Drive
Kaysville, UT 84037

Be sure to include that the order is for the MP3 CD maker, your complete name and address, phone number, and E-mail address.

I do not want to use my credit card on internet, what can I do?

If customers would like to pay by check or money order, they can send it to the address listed below. They can also fax their credit card orders to us as well. Our fax number is (801) 497-9456.

If they want to pay by check, they only need to include their name, address, phone number, and email address along with the product name. They can mail it to our address:

Qwerks.com Inc
1648 Willow Dr
Kaysville UT 84037
USA

