

For Programs made with Click & Create ...

Simply left-click on the UNINSTALL icon in the program group for that game. Follow the on screen instructions.

For Programs made with Klik & Play ...

FROM WINDOWS 3.x :

- 1) Go to File Manager
- 2) Double left click the directory which contains the program.

* This is c:\windows\games if you did not change it at the time of installation.

- 3) Delete the main program name and its related files.

Note: The related files all start with the same name as the main program.

Example: filename.gam
 filename.img
 filename.mtf
 filename.mus
 filename.snd
 filename.exe
 filename.wri

- 4) If this was your only program made with Klik & Play, then you should also delete 2 other files.

KNPS.DLL and KNPG.DLL

These programs are usually located in the Windows directory. Use File Manager to find these files and then delete them.

- 5) Finally, while in Program Manager, highlight the icon for the game being deleted. The name under the icon should be highlighted and there should be no menu exposed on the icon. If there is, hit the ESC key. Then hit the Delete key to remove the icon

from the desktop.

FROM WINDOWS 95

- 1) Left-Click on the My Computer icon.
- 2) Left-Click on the drive C icon
or whatever drive contains the program.
- 3) Left-Click on the directory which
contains the game to be removed.

* This is c:\windows\games if you did
not change it at the time of installation.

- 4) Hilight all of the files which begin with
the same name as the program to be removed.

Note: The related files all start with
the same name as the main program.

Example: filename.gam
 filename.img
 filename.mtf
 filename.mus
 filename.snd
 filename.exe
 filename.wri

(You can hilight more than one file by either
holding down the CTRL key and left-clicking
once on the icon or by dragging a box around
the files.)

- 5) After you have hilighted the desired files, hit
the delete key. You will be asked if you want to
send these files to the Recycle Bin. Say YES.
- 6) IF THERE ARE NO MORE GAMES ON YOUR COMPUTER THAT
WERE MADE WITH KLIK & PLAY, you can also remove
the files KNPS.DLL and KNPG.DLL from the Windows
directory.
- 7) If you created a shortcut to the game, remove
that by Right-clicking on the icon on the Desktop
and then left-clicking on Delete.
- 8) Fianally, you need to remove the program from
your Start Menu. Right-click on an empty grey
portion of the TaskBar. Then left-click on the

word "Properties" at the bottom of the little menu. Choose "Start Menu Programs" on the screen that appears. Then choose "Remove" .

9) A "tree" is displayed. Find the folder which contains the program. Left-click once on the "+" sign to open the folder. Right-click once on the program name to high-light it. Then left-click the "Remove" button. Follow the instructions.

10) Close all windows when you are finished.