

**ModePro**

<b>COLLABORATORS</b>
----------------------

	<i>TITLE :</i> ModePro		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		December 2, 2024	

<b>REVISION HISTORY</b>
-------------------------

NUMBER	DATE	DESCRIPTION	NAME

# Contents

<b>1</b>	<b>ModePro</b>	<b>1</b>
1.1	ModePro Manual . . . . .	1
1.2	Introduction . . . . .	2
1.3	Instructions . . . . .	2
1.4	Programs/Screens cycle gadget . . . . .	3
1.5	Promotion List . . . . .	3
1.6	Priority Slider . . . . .	3
1.7	Use Program Default . . . . .	3
1.8	Promote Monitor Type . . . . .	4
1.9	Promote Screen Mode . . . . .	4
1.10	Use Screen Mode Requester . . . . .	4
1.11	Select Screen Mode... gadget . . . . .	5
1.12	AutoScroll check box . . . . .	5
1.13	3-D Look check box . . . . .	5
1.14	Width gadget . . . . .	5
1.15	Height gadget . . . . .	6
1.16	New gadget . . . . .	6
1.17	Remove gadget . . . . .	6
1.18	Overscan cycle gadget . . . . .	6
1.19	Name gadget . . . . .	6
1.20	Screen Mode display . . . . .	6
1.21	Default Pens . . . . .	7
1.22	Pen List . . . . .	7
1.23	Current Pen Name Display . . . . .	7
1.24	Pen Value . . . . .	7
1.25	ToolTypes . . . . .	8
1.26	WARNING!! . . . . .	8
1.27	Details . . . . .	8
1.28	My Address . . . . .	8
1.29	Menus . . . . .	9
1.30	History . . . . .	9

# Chapter 1

## ModePro

### 1.1 ModePro Manual

ModePro 2.2

08/03/94

Copyright 1994.

All Rights Reserved.

by Michael Rivers

For WB 3.x users and possibly WB 2.1

A program to promote screen mode, make screens autoscroll, and  
give old screens the WB 2+ 3D look.

Intro

Instructions

--WARNING--

Details

My Address

History

Sorry about the piss poor instructions in advance!

This software may be freely distributed as long as the following criteria  
are met:

1. The following files must be included  
ModePro  
ModePro.Guide
2. No fee may be charged for this software, media fee not included so  
long as the media fee is reasonable
3. This software may not be included in any commercial software  
package without my written permission

This software is DonationWare. There is no charge for this program but  
you are more than welcome to send me money (USA \$ please).

Should any software house get ahold of this and is looking for a programmer  
please contact me, I need a job.

---

## 1.2 Introduction

ModePro is an application specific screen "promoter" for WB 3.0 and above. It was created because of some pathetic commercial software companies won't get off their ass and bring their software up to date. It really pisses me off to pay over \$300 for software and not even be able select a decent screen mode. So, until the software houses wake up and really update their software, your stuck with this.

## 1.3 Instructions

Here are three ways to start ModePro:

1. Double click its icon
2. Type its name in at the shell prompt and hit enter
3. Drop its icon in the WBstartup drawer and it will start on the next reboot.

Menus

ToolTypes

ModePro interface.

To bring up ModePros interface use one of the following:

1. Use the hotkey (default left-amiga p)
2. Use the Commodities Exchange program
3. Run the program again.

This is a archaic representation of the interface:

```
[.] [ModePro X.XX blaablaablaa -- Hotkey <hot key here> (see ToolTypes) ] [ ]
```

1. [C  program names ]	7.o Use Program's Default	18. [Default Pens]
-----	8.o Promote Monitor Type	-----
	9.o Promote Screen Mode	
	10.o Use Screen Mode Requester	
	11. [ Select Screen Mode... ]	
2.	12. [ Screen Mode Display ]	19.
	13.Width: [### ] 15.[/] AutoScoll	
	14.Height: [### ] 16.[/] 3-D Look	
	17.Overscan: [C  Text Size ]	
3. [ Name Gadget ]		
4. [ New ] 5. [Remove ]		20. [xxxxxxx] [###] 21.

1.Names Cycle Gadget	12.Screen Mode Display
2.Promotion List	13.Width:
3.Name Gadget	14.Height:
4.New	15.AutoScoll
5.Remove	16.3-D Look
6.Priority Slider	17.Overscan
7.Use Programs's Default	18.Default Pens
8.Promote Monitor Type	19.Pen List
9.Promote Screen Mode	20.Current Pen Name Display
10.Use Screen Mode Requester	21.Pen Value

11.Select Screen Mode...

if you can't figure out the correct program name or screen name  
 use one of the catch menus then run the problem program, its name ↔  
 will  
 be added to the appropriate list.

## 1.4 Programs/Screens cycle gadget

Programs/Screens cycle gadget

ModePro knows which screens to promote by two lists.  
 This gadget switches which list is being displayed.  
 There are two lists:

One is a list of program names.

When a program in this list opens any screen, ModePro promotes it

The other is a list of screen names.

When any program opens a screen named in this list, ModePro promotes it

NOTE if a program opens a screen and both the program's name and the  
 screen's name are in the promotion lists, ModePro promotes using the  
 promotion information for the SCREEN NAME.

## 1.5 Promotion List

Promotion List

-----  
 This list contains the screen and program names that should be  
 promoted. When using wildcards remember that the list is scanned  
 from top to bottom, so if "#?" is in the list no other entries  
 below it will be checked. You should also not use "#?" in the  
 screen promotion list, as the screen name list has priority  
 over the program name list and thus will override any settings  
 in the program name list(although theres nothing stopping you from  
 doing so). Letter case is ignored as of v1.5, therefore CAT=cat.

## 1.6 Priority Slider

Priority Slider

-----  
 This slider is used to adjust an entries priority

## 1.7 Use Program Default

#### o Use Program Default

-----

This option is useful in the case that you may not want the dimensions, screenmode, or overscan changed but would like a 3D or autoscrolling screen.

see :

AutoScroll and 3-D Look

## 1.8 Promote Monitor Type

#### o Promote Monitor Type

-----

This option promotes a screen to an equivalent resolution under another monitor type (I think) specified in the text gadget. Therefore you can promote an NTSC screen to say...an equivalent EURO36 screen, making interlaced screens more bearable.

Note this is a direct monitor promotion there is no resolution promotion so the results may not be what you expect.

## 1.9 Promote Screen Mode

#### o Promote Screen Mode

-----

When ModePro promotes a screen with this option it will promote it with the specific screen type listed in the text gadget. You may also set the width height and overscan of the screen but the number of colors will be taken from the program that requested the screen .Use the Select Screen Mode... gadget to select the screen mode of your choice.

Also make sure the display mode can handle the number of colors the application program wants, forcing a program to open a 32 color hires screen on and Old Chip Set or Enhanced Chip Set machine will not work.

Warning: some shitty programs can't handle screen sizes other than what is coded into the program, some may work, some may crash, some may put crap all over the screen.

## 1.10 Use Screen Mode Requester

#### o Use Screen Mode Requester

-----

When ModePro promotes a screen with this option it will bring up a Screen Requester for you to pick a screen mode.

Note that you can use the Select Screen Mode... gadget to select the initial values when the screen mode requester opens.

---

If you are using a non-AGA machine you may find that the list of screen modes has been limited, this may be a result of the program asking for a screen depth not available at higher resolutions.

When the screen mode requester appears because of this option no other program may open a screen until the requester is closed.

## 1.11 Select Screen Mode... gadget

Select Screen Mode... gadget

-----  
Use this gadget to select a screen mode, monitor type, or the default settings for the screen mode requestor.

## 1.12 AutoScroll check box

AutoScroll check box

-----  
This option will make a promoted screen AutoScroll.  
Note however that if a screen was originally set to autoscroll you cannot force it to not autoscroll by leaving the checkbox unchecked.

## 1.13 3-D Look check box

3-D Look check box

-----  
This will give a promoted screen the WB 2+ 3D look.  
Note you cannot force a screen to not have the 3D look by leaving this box unchecked.

Also, if a two color screen is requested and this option is checked the screen will be opened with four colors instead, the 3d look requires four colors. I have seen one program where this 2 to 4 color promotion will not work: dpaint.

## 1.14 Width gadget

Width gadget

-----  
This gadget allows you to specify a width using the last two promotion options



## 1.15 Height gadget

Height gadget

-----

This gadget allows you to specify a height using the last two promotion options.

## 1.16 New gadget

New gadget

-----

Creates a new entry in the list

## 1.17 Remove gadget

Remove gadget

-----

Removes the highlighted entry in the list

## 1.18 Overscan cycle gadget

Overscan cycle gadget

-----

This gadget allows you to specify the overscan type using the last two promotion options.

## 1.19 Name gadget

Name gadget

-----

This allows you to edit then highlighted name in the list.  
AmigaDos wildcards may be used

## 1.20 Screen Mode display

Screen Mode display

-----

Simply displays the active screen mode

## 1.21 Default Pens

Default Pens gadget

-----  
This will set the pen list to their default values. The default values will be taken from the default Public screen (usually Workbench)

Disabled if 3-D Look is not selected.

## 1.22 Pen List

Pen List

-----  
This displays the pen names and their values

Pens	OS	desc.
Detail	1.x	obsolete
Block	1.x	obsolete
Text	2.0	Text on background
Shine	2.0	Bright edge on 3d objects(gadgets, windows...)
Shadow	2.0	Dark edge on 3d objects
Fill	2.0	Active window border/Selected gadget fill
Fill Text	2.0	Text over Fill
Background	2.0	Background color of unselected gadgets and inactive windows borders
Highlight Text	2.0	Highlighted text color
Bar Detail	3.0	Text color in screen title bar
Bar Block	3.0	Color of screen title bar
Bar Trim	3.0	Trim under screen title bar

Disabled if 3-D Look is not selected.

## 1.23 Current Pen Name Display

Current Pen Name Display

-----  
This displays the current pen name your editing.

Disabled if 3-D Look is not selected.

## 1.24 Pen Value

Pen Value

-----  
This gadget allows you to change the value of the pen displayed in the Current Pen Name Display gadget.

Disabled if 3-D Look is not selected.

## 1.25 ToolTypes

Here is the list of supported tooltypes:

```
-----  
CX_POPUP=YES/NO    (default NO)  
CX_POPKEY          (default lcommand p)  
CX_PRIORITY=#      (default 0)  
DONOTWAIT
```

Information on these tooltypes is probably in the Workbench manuals under "Commodities".

## 1.26 WARNING!!

WARNING

-----  
Use this program at YOUR own risk!

Some really shitty programs will have problems when being put on screens that are not the size they were expecting.

These "programs" may crash!!! So your going to have to do some trial and error.

## 1.27 Details

This program patches the OpenScreen and OpenScreenTagList functions in the intuition library. This software does not replace the functions nor modify any data passed to it and should be completely system compatible

This is basically what it does:

OpenScreen() simply calls my OpenScreenTagList with parameters set as ↔ appropriate

OpenScreenTagList() creates a small taglist with the attributes that are going to be modified, if a taglist was passed to the function the taglist is linked with TAG\_MORE to the end of the new taglist. The function then passes the NewScreen structure (if any) and the address of the new taglist to the original intuition OpenScreenTagList().

This patch can be safely removed as long as no other program patches the functions after this program does. This program will notify you on exit if another program has patched over it.

## 1.28 My Address

You may send money, suggestions, error reports, complaints and oh yea money to:

Michael Rivers  
4302 Wisconsin Court ( please write out Court don't put CT or it gets  
sent to the wrong street )  
Tampa, FL, USA 33616

you might also be able to reach me on

C-Link at Vermin@911:6000/14.0  
USENET at mdrivers@tbag.tscs.com  
FIDONET at Michael Rivers@1:377/71  
AMIGANET at Michael Rivers@40:719/14.0  
(no E-Mail bombs please)

I hope those are correct, I'm new to this modem thing!

## 1.29 Menus

Menu

\_\_\_\_\_

Project

Open	Open a mode promotion file
Save As	Save current settings to a file
-----	
Save	Make current ModePro settings permanent
Last Saved	Load permanent settings
-----	
Enabled	Indicates whether or not ModePro is active
-----	
About...	Obvious
-----	
Hide	Hide interface
Quit	Quit ModePro (all mode promotion stops)

ScreenCatch

Catch Programs  
Catch Screens

If either of these options is enabled, when a program opens a screen, either the program's name or the screen's name or both will be added to the appropriate promotion list. This is useful when you can't figure out the correct name to put in the list.

### 1.30 History

## History

\_\_\_\_\_

version	date	desc.
v 2.2	10/08/94	
v 2.1	8/03/94	Bug fix:Forgot to free ASL file requester memory when

---

		ModePro was quit.
		More code cleaning.
v 2.0	7/07/94	New features: user selectable pens for 3-d look commodity hotkey support added.(finally)
		Bug fix: File requester now works correctly. (forgot to add a / between the path and the filename when required)
v 1.5	6/04/94	Bug fix: Stupidity error. I forgot to free data when an entry was removed or when the program was ended.
		New features: AmigaDos wildcards can now be used. Priority slider.
v 1.3	5/21/94	Bug fix: ModePro wouldn't Unlock the pubscreen that its window was on if another program opened a screen while ModePro's window was open.
		Minor menu work
v 1.2	5/19/94	Tried to make code WB2.1 compatible
v 1.1	4/18/94	ModePro is now a commodity. minor code cleaning. spelling correction.
v 1.0	3/30/94	Initial Release.

---