


# Win Bar Clock 4.1a <sup>TM</sup>

*Title Bar Clock*



Copyright (C) 1991-1995 By G. L. Liadis Software, Inc.  
World Wide Rights Reserved.

=====

QUESTION --- UPDATES \*\*\*\*\*CALL OUR BBS \*\*\*24 HOURS PER DAY\*\*\*  
SUPPORTS SPEEDS UP TO 28,800 THE PHONE NUMBER IS  
\*\*\* 614-888-4749 \*\*\* 5 LINES

=====

**NOTE:** Registered Win Bar Clock or any other of our programs with European Currency (Cash Only), or a check drawn on an US bank.

**Registration:**German DM = 40.00 including shipping (Cash Only).

AFTER INSTALATION CLICK WITH THE RIGHT MOUSE BUTTON THE "CLOCK BAR" TO CONFIGURE WIN BAR CLOCK.

Win Bar Clock creates a WBARCLK.INI file if your Windows directory if you get any error messages delete this file and restart Win Bar Clock.

**NOTE:** The Arcade Game of Win SpaceWars v4.1 (WSPACE.ZIP) Will Be Available on 11/94 on CIS, AOL and many other BBS's World Wide.

**\*\*NEW\*\*** Win SetTime v5.1 supports all US USNO, NIST & European Atomic Clocks, AUSTRIA, ITALY, SWEDEN and others,Dials with your modem gets the universal time and date and automatically, updates your PC's Clock and Calendar EXACTLY.  
Win SetTime Was featured in the "SUPERIOR SHAREWARE" section of Windows Magazine the September issue of "INSIDE WINDOWS" Magazine and many others.

To register on Compuserve GO SWREG select KEYWORDS then enter LIADIS.

You will also receive the folowing programs **\*\*FREE\*\*** with your registration of Win Bar Clock 4.1.

1) Win Player



2) Win Viewer



### 3) Win Memory Game



**Read the README.WRI file for a list of our newest shareware programs.**

**NOTE: After you run Win Bar Clock if you want the Monitor Bar to be in the Title Bar also run TCLK.EXE.**

**Description:** Win Bar Clock 4.1 (tm) (Title Bar Clock) is a utility for the Windows environment that displays information such as the time, date, system resources, or any text message

- > in the title bar of the active window, and/or
- > in a floating (movable) "Bar Clock"

### **Features:**

- Customize all functions
- Display the date, time, memory, and system resources in any format
- Display personal text message in the title bar of the active window
- Set an unlimited number of alarms
- Run timers with which to track sessions and online fees
  
- Change colors (can be up to 16 million)
- Select font type and size (TT ATM FON)
- Speed dial and phone number database (supports com ports 1 - 4 )
- Edit system files (BAT, SYS, and INI files)
- Quickly access system commands *Exit* and *Restart Windows*
  
- Jump to DOS or reboot
- Run programs from within any application
- Display month calendar
- Configure all functions with Center Console
- Display system information -- everything you want to know about your hardware and operating software setup, including:
  - free and used disk space on any drive...
  - clusters, sectors, bytes...

video mode, processor, display driver, keyboard...  
Windows & DOS version, language...  
time length of your current Windows session...  
and much more...

**System Requirements:** Windows 3.1  
VBRUN300.DLL in directory C:\WINDOWS\SYSTEM  
You can download it from most online services.

## Installation:

- (1) Create a directory (C:\WINDOWS\WBARCLK) and copy these files into it:
- > WBCHELP.WRI This file
  - > WBARCLK.EXE Win Bar Clock executable
  - > WCSETUP.EXE Win Bar Clock Setup file
  - > **README.WRI Information File (Please read it)**
  - > ALARM.WAV Wave file for the alarm you may replace it with your own.
  - > LICENSE.WRI License information

***NOTE:** do not delete **WCSETUP.EXE**. This is a Win Bar Clock 4.1 (tm) system program.  
If you delete it, the program will not run.*

- (2) Move **DISKINFO.DLL & VBCTL3D.VBX** into the WINDOWS\SYSTEM directory.

- (3) To automatically run Win Bar Clock 4.1 (tm) when you start Windows, set up an icon for WBARCLK.EXE in your StartUp program group. Restart Windows.

If it is installed properly, the Clock Bar will appear in the middle of your screen.

## Main Menu:

To access the main menu, click once on the floating Clock Bar with the **right mouse button**.

The main menu contains several options:

- SetUp**
- System Commands**
- System Info**
- Quick Execute**
- Speed Dialer**
- Calendar**
- About**
- Start Timer**
- Exit**



**Note:** In this documentation, the clock symbol designates main menu items.



## SetUp:

SetUp contains  
seven submenus:

**Monitor SetUp**  
**Title SetUp**  
**Speed Dial SetUp**  
**Quick Exe(cute) SetUp**  
**Alarm Settings**  
**Edit System Files**  
**Center Console**

**Monitor SetUp:** Customize the floating Clock Bar.

Time, Date, Memory or Resources boxes: Check the item(s) you want displayed in the floating Clock Bar.

Format pull down menus: Set display preferences for time, date, or memory.

Label text boxes: Type messages for display in the Clock Bar.

Always On Top box: Keep the Bar on the top window layer.

Save Monitor Position box: Boot up Bar at the current screen position.

Portrait or Landscape : Display clock information in vertical or horizontal format.

**Title SetUp:** Customize the title bar display.

Time, Date, Memory or Resources boxes: Check the item(s) you want displayed in the title bar.

Show Title Bar box: Run Win Bar Clock 4.1 in the active window title bar.

Right, Left or None Position buttons: Toggle the position of the title bar information.

Format pull down menus: Set display preferences for time, date, or memory.

Label text boxes: Type messages for display in the title bar.

**Speed Dial SetUp:** Modify the phone database.

Add button: Access the *Edit Dial* box and type your new entry for the database.

Valid characters for phone numbers are arabic numerals, spaces, comma, and dashes. Example: 614 888-4449 or 614 888,4449. include the prefix if you need to access an outside line from a PBX .

Delete button: To remove an entry from the list, select it, then click *Delete*.

Edit button: Select the entry, click the *Edit* button, then type your changes in the *Edit Dial* box.

Tone or Pulse option buttons: Select your preference for dialing.

Com Port option buttons: Select Com1, 2, 3 or 4.

OK button: Save phone database while closing the *Dial Setup* box.

**Quick Exe SetUp:** Configure programs that can be run from **Quick Execute**.

Add button:

- 1) Click the *Add* button to access the *Select File* dialog box
- 2) Enter the full name of the program into the *Application Name* box.
- 3) Select the executable file from the *Command Line* box or by clicking on the directory windows.

Delete button: To remove a name from the list, select it, then click *Delete*.

**Alarm Settings:** Alarm beeps and displays when the set time is reached.

Add button: Access the *Add New Message* box.

Date text box: The current date is listed; change it to the desired date.

Time text box: The current time is listed; change it to the desired time.

Message text box: Delete the default message and type your own message.

Active check box: Toggle the alarm on and off.

Edit button: To change an existing message, select it, then click *Edit* to access a dialog box similar to the one described above.

Delete button: To remove an alarm setting, highlight it, then click *Delete*.

### **Edit System Files:**

SelectFile option buttons: Select the system file you wish to edit.

(File)Sections drop list: To go to a particular section of the selected system file, choose it by pulling down the drop list.

Save button: Keep the changes you made to your system files.

Exit button: Close the window without saving.

### **Center Console:**

Access the main menu, which appears as a floating button bar.



### **System Commands:**

Select the standard commands from the menu..

- > DOS prompt -- return to Windows by typing "exit" at the DOS prompt.
- > Exit Windows
- > Restart Windows
- > Reboot your system



### **System Information:**

Display a bonanza of fascinating data regarding your

computer hardware and software setup.





### **Quick Execute:**

Single-click to boot programs that you added using **SetUp; Quick Exe Setup**.



### **Speed Dialer:**

Speed dial a phone number that you added using **SetUp; Speed Dialer Setup**.



### **Calendar:**

Display month calendar.

To advance in one year increments, click on the horizontal scroll bar.

To advance in one month increments, click on the scroll arrows.



### **About:**

Display information about the brilliant creators of Win Bar Clock 4.1 (tm)



### **Start Timer:**

Run timer in Bar Clock.

After the timer is started, the **Start Timer** menu item changes to **Timer Status**.

#### **Timer Status:**

Charge per minute text box: If you are timing a charged online session, type your per minute rate into the box.



### **Exit:**

Close Win Bar Clock 4.1 (tm)

**QUESTIONS OR SUGGESTIONS?**

Contact us at the following addresses:

**USA**

**G. L. Liadis & Associates  
5167 1/2 Saling Court  
Columbus, Ohio 43220**

**EUROPE**

**G. L. Liadis  
G. L. Liadis Software, Inc.  
Agali Beach Resort  
Kardamyla, Chios 83100  
GREECE**

**Electronic Addresses**

**CompuServe: 72274,3252  
America On Line: G L Liadis  
Internet: GLLiadis@aol.com  
BBS 614-888-4749**

***Thanks for your support.***