

Network Services

Change export permissions

4padPointRule2.eps ↗

When you set up a file server to export directories, you also specify which computers can access them—with read/write, read-only, or root privileges.

You can change these permissions at any time.

18770_PointRule2.eps ↗

1 Log in as root on the computer with the file server.

If you don't log in as **root**, you can enter the **root** password if the User Authentication panel appears.

1PointDashedRule3Black.eps ↗

2 Double-click NFSManager in /NextAdmin.

427113_PointDashedRule3Black.eps ↗

3 Select a directory at the top of the Exported Directories window ;../Reference/Tools/NFSManager/NFSManagerPanels/ExportedDirsWindow.rtf;↗.

If this window isn't open, choose Export From in the NFSManager menu, select a domain, and click OK.

964182_PointDashedRule3Black.eps ↗

4 Type the name of each computer you want to have Read Only Access and click Add. Or select a name from the Read Only Access list and click Remove.

You can type a host name, alias, or netgroup name.

662663_PointDashedRule3Black.eps ↗

5 Type the name of each computer you want to have Read/Write Access and click Add. Or select a name from the Read/Write Access list and click Remove.

As in step 4, you can type a host name, alias, or netgroup name.

559317_PointDashedRule3Black.eps ↗

6 Type the name of each computer you want to have root privileges on the computer. Or select a name from the Root Access list and click Remove. Be sure the computers you add to this list are secured from unauthorized root logins.

814654_PointDashedRule3Black.eps ↗

7 Click OK.

[465043_PointDashedRule3Black.eps](#) ↗

These permissions apply the next time the computer starts up.

[2PointRule.eps](#) ↗

Related topics (*click a* [LinkDiamond.tiff](#) ↗)

[706575_pt-Xref-Rule2.eps](#) ↗

Concepts

Want to know more about export and import permissions?

[;AboutNetworkFiles.rtf](#); ↗

About network files

[727921_pt-Xref-DashedRule2.eps](#) ↗

How to

You may also need to change the access options for the NFS client computers.

[;ChangeImportPermissions.rtf](#); ↗

Change import

permissions