

Software House Parsley Original Screen Saver - Version 1.00

Copyright 1995 (C) Software House Parsley
(C) Kouiji Maeda

Introduction

This program is a screen saver module designed to run on the Microsoft Windows 3.1 system, or Windows 95 system.

Operating Requirements

Microsoft Windows 3.1 system, or Windows 95 system.

At least 4MB of free memory (screen saver appearance will vary in accordance with the size of your display and the number of colours your machine can run).

A display capability of at least 256 colours.

Note 1

It is necessary to have enough CPU and memory power available in your machine to display full-colour BMP images. If your machine proves unable to do so, you are advised to use Search to find the appropriate directory in which they have been installed, and to delete the BMP files forthwith.

Note 2

When the screen saver images cut in on a computer running more than 256 colours, they may occasion a palette change. You can remedy this by clicking CHANGE DISPLAY TO BLACK SCREEN to ON.

Installation and Removal

Set Up

Picture Group

Set Up Button

Directory

File name

Referring to sub directories

Random selection

Image Pattern Group

Selecting the method of image patterning

Image pattern

Fast
Normal
Slow
Tile Option
Centre Option
Cutting off black area within image space
Time delay before image cut-off
Number of images on screen

Password selection group

To prevent screen saver override without password entry.

Password protected
Set Password

Installation

1. Using File Manager, copy the files marked PSL_SSV1.SCR and PSL_SSV1.HLP to your screen saver directory.
2. Select Desktop from the Control Panel, and scroll through the NAME menu on the SCREEN SAVER window. Select 'PSL SS. Ver 1.00' from the menu, then click OK. Your Parsely screen saver should now be installed.

Removal

1. Delete PSL_SSV1.SCR and PSL_SSV1.HLP from the Windows directory.
2. Open the editor files on your machine (eg. CONTROL.INI) and delete the following filenames:

```
[ScreenSaver.psl_ssv1]
BitmapDirectory=
SubDirectory=
Random=
View Type=
Center=
Tile=
ClearBackground=
Pause=
Speed=
PWProtected=
Bound=
BoundBitmap=
```

Please take care not to delete the relevant files from the other Windows screensavers, especially as regards the password file.

[ScreenSaver]
Password=

Your Parsley screensaver should now be uninstalled.

Setting up the Screen Saver

Once you have installed your screen saver, select Control Panels from the Main Windows Menu and open Desktop. On the Screen Saver part of the Desktop menu, you can select PSL S.S. Ver 1.00 from the Name menu, and use click the SET UP (U) button to alter it. Click OK before quitting the Screen Saver menu to preserve the changes made. Please remember that changes will not be preserved within SET UP unless you press OK before exiting.

If any problems remain unresolved with the Microsoft Screen Saver, try clicking the dialogue box HELP (H) on the menu.

Testing Your Screen Saver

To test your screen saver before selecting it, press TEST (E) on the menu.

Note

Parsley Software House accepts no responsibility for loss or damage to data on the hard disc through improper use of this screen saver or non-adherence to the installation guidelines as set out above.

Directory

Selects the directory referring to the BMP files.

File name

Selects the bound BMP

It is not possible to select a non-bound image pattern.

Refer to subdirectory

To use these screensavers, the file must be in the same directory. If not in Windows or SYSTEM, the directory in which they are located must be included in your path.

Random selection

Select the the image pattern to Random by selecting the BMP file from the directory.If the subdirectory is selected again, it will show that the subdirectory has been set to random selection.

Image pattern

Set up CG imaging method.

If Random Imaging is selected, the sequence will commence with '*' and be randomised thereafter.

Fast Normal Slow

Selects the time between different CG images appearing on screen.

Note: While in use this will not effect the speed of the CPU, display card, display driver, etc.

Tile option

Check in order to fit CG images to your screen size and view all in a cascade. Where you have also selected Centre option, the graphics will appear around the central tile.

Centre Option

Select this to ensure that CG images smaller than the screen are properly centred. Where you have also selected Tile option, the graphics will appear around the central tile.

Cut off black area within image space

Select if you wish the previous image to be 'blacked-out' by each successive image.

Selects the time between different CG images appearing on screen.

Selects the number of images used on the CG screen saver. The number ranges from 1-10. This can be changed within the bound image dialogue box.

Password Protected

Select the Password Protected check box to turn on password protection. when password protection is turned on, you cannot return to Windows from the screensaver until you type the password.

Note: Please take care not to forget your password.

Set Password

Selects the password to enable return to Windows when in Password Protected mode.

Old Password

A new password may not be entered until the previous password has been entered.

New Password

Sets New Password

Retype New Password

A new password will not be accepted until it has been typed in twice.

