# TapeMate Version 1.00.14 Release Notes. June 1996.

## If you Need to Contact the Author.

you can do so by writing to:- Stephen Cullen

Elvaron Mediasoft Services, 4 Andersonstown Drive, BELFAST BT11 8FW, County Antrim, Northern Ireland.

or by phoning or sending E-mail to:- Telephone/Fax:

01232 616304

(preferably after 6.30 p.m.)

CompuServe ID: 100046,2157

Internet Address: 100046.2157@compuserve.com

AOL: elvaronms@aol.com

#### **TapeMate Features.**

- Intuitive easy to use interface.
- Effortlessly create Cassette Inlay Cards (index/J-Cards) for you cassette cases.
- Have full control over typeface information for Cassette Inlay Cards.
- Print Face Labels for your tapes / cassettes
- · Print Divider Cards for your compact disc's / cassettes
- · Print in Colour.
- · Save, load and preview Inlay cards.

## **Installing TapeMate**

**NOTE**: If you use a virus protection program or have any other programs running on your computer, close them down before using the TapeMate Set-up program. The Set-up procedure may not function correctly with other programs loaded into memory. Once installed your can safely run other programs along with TapeMate.

### From Program Manager

- · Start Microsoft Windows.
- Insert the TapeMate 'Installation Disk' into drive A: or B:
- From the File Menu in Program Manager, choose Run.
- Enter a:\setup or b:\setup in the dialogue box which appears on screen.
- Click the OK button or press ENTER.
- · Follow the Set-up Instructions below.

#### From File Manager

- Start Microsoft Windows.
- Insert the TapeMate 'Installation Disk' into drive A: or B:
- Open File Manager by double-clicking on its icon.
- Select the toolbar icon representing the required drive A: or B:
- On the right hand side of the screen is the file list, locate and double-click on the filename 'SETUP.EXE'.
- Follow the Set-up Instructions below.

#### **Set-up Instructions**

Following on from whichever procedure used above, you will then be asked to:-

- Supply the destination directory in which you want TapeMate installed (Figure 1). The
  default directory is C:\text{TAPEMATE}, but this can be changed to another directory if the
  default is not suitable.
- · Click Continue to move on.

Set-up will then start copying the necessary files to the specified destination directory. A Program Manager Group containing the TapeMate Program Icons will then be created for you. To start TapeMate, simply double-click on the icon and the application will load.

#### Starting-up TapeMate.

If you are still in DOS, start Microsoft Windows by typing Win at the DOS C:> prompt, then press [ENTER]. This will load the Windows Operating Environment.

Once Windows is loaded, locate and double-click on the TapeMate icon. This will activate the program and load it into memory. Once loaded the About dialogue will be displayed. Just click the Continue button to proceed.

#### Compuserve Users.

TapeMate can also be registered via CompuServe. To register GO SWREG Select the 'Register Shareware' option. Search by Author ID: **100046,2157** or Registration ID: **6915**. This will take you to the appropriate program. CompuServe will guide you through the rest! You will be automatically billed \$15 + \$8 handling (service fees, etc.) on your next CompuServe bill.

Once you have registered, I will be notified immediately with your details. Usually within 2-3 days you will be sent an Email. This is to acknowledge receipt and provide notification that the goods have been dispatched to you.

#### Documentation.

Complete documentation is provided on-line in Windows Help format. This can be called at any time from within the TapeMate program or by double-clicking on the TapeMate Help file in File Manager. An icon is also created and placed in the TapeMate Program Manager window when the program was installed.

# Changes and Fixes List.

**1.00.04** This release fixes a problem in the General / Print Options dialogue. If you previously tried to print out tape divider cards TapeMate tended to print dividers for CD's. This was caused by the index for the tabs not being set correctly. This is now cured.

- **1.00.06** Certain controls which contained numeric values caused problems when that control lost the focus. This was caused by moving from a control when it did not contain a value which led to unpredictable results as far as margins etc. were concerned. A default value is now displayed whenever a control without a value looses the focus.
- **1.00.08** Changed the default text colour for the Main Title and Side Descriptor areas from blue and red respectively to black. When these areas display text in colour as opposed to just black text then in some cases when printing to a black and white printer the coloured text fails to print due to the printer not being able to handle coloured text. Some printers will dither the coloured text to a shade of gray.

If you experience this problem where a specific area of the inlay is not printing then try changing the text for that area to black.

- **1.00.10** Fixed a bug which caused a program crash. This occurred whenever the save option of the cassette inlay module (or the save toolbutton) was chosen without first loading or using the Save as... option to specify a name for your inlay. Also added the facility for instant access to the registered version after receipt of registration.
- **1.00.12** Fixed a small bug related to removing the last track on either side of a cassette inlay card. The problem was that when a track occupied more the one line, you sometimes had to hold in the ALT button and click three or four times to remove the last track. You should of course only have to click once. This is now working correctly.

In the **Default / Print Options** dialogue an additional text box has been added for storing the value of a 2nd left margin setting. This applies to the printing of Cassette Face Labels and allows you to specify the margin for the rightmost or 'Side B' Face Label. This is for my American friends who use the 'Letter' paper size of Avery Labels as opposed to the European based 'A4' size. The reference for the Avery labels are **L7655** (European A4) and **#5198** (American Letter).

**1.00.14** Added a small enhancement to the cassette Face Labels option for printing labels on an ordinary piece of paper. On the Face Labels tab in the General / Print Options dialogue there's an option to print the outline of a label. This has been enhanced to include and print an outline for the centre piece of the label. This will assist when it comes to trimming the labels before attaching to the actual cassette.

\_\_\_\_\_

This document is copyright 1995-96 Stephen Cullen, Elvaron Mediasoft Services. All Rights Reserved.