

# To install

## Library:

1. Copy ATRIOUS.DLL to your WINDOWS\SYSTEM directory. (Include this file in your distribution)

## Help file:

1. Backup the current help file index (c:\Program Files\Borland\Delphi 2.0\BIN\Delphi.Hdx) to another location.
2. Run the HELPINST application. (c:\Program Files\Borland\Delphi 2.0\Help\Tools\HelpInst.Exe)
3. Choose FILE/OPEN.
4. Enter the Delphi.Hdx file and location. (c:\Program Files\Borland\Delphi 2.0\BIN\Delphi.Hdx)
5. Choose KEYWORDS/ADD KEYWORD FILE.
6. Enter the VideoLab.Kwf file and path.
7. Choose OPTIONS/SEARCH PATHS.
8. Enter the VideoLab.Kwf path and the path to the Delphi Help files. (Should look something like: c:\VideoLab;c:\Program Files\Borland\Delphi 2.0\Help\)
9. Choose FILE/SAVE then exit the application.

## Component:

1. From Delphi Choose COMPONENT/INSTALL.
2. Choose the ADD button.
3. Browse for your copy of VideoLab.Dcu.
4. Choose OK button.