

Reviewer Mode:

Selecting the Reviewer mode will cause the Control panel to look similar the following. Reviewer mode is used to replay data taken in the Simulation mode.

paste_23.tiff ↵

The box labeled *Time* displays the time value at the current stage of the replay. The box labeled *Real time between frames* allows the user to set the wait time before the computer displays the next frame while replaying. The slider labeled *Frame* lets the user set the current frame to be displayed from the saved data of the simulation. This slider also updates to indicate what frame is being played when the simulation is replaying. The *Play* button starts replaying the simulation, the *Stop* button stops the replay, and the *Step* button steps through the replay one frame at a time. You can reverse time in the Reviewer mode using the toggle switch under the label *direction* which will toggle from *Forward* to *Backward*. The *Step by* indicates the number of frames the frame counter will increase or decrease by for each step. When the Reviewer reaches the beginning or end of the simulation, it will wrap around to the end or beginning respectively.

