

IntelliPoint Setup Help Contents

[IntelliPoint Setup Help](#)

[Custom Setup Help](#)

[Change Directory Help](#)

[Pointer Options Help](#)

[Miscellaneous Options Help](#)

IntelliPoint Setup Help

From the previous dialog box,

▶ Choose Continue to continue with Setup and install the Microsoft IntelliPoint software on your hard disk.

- or -

▶ Choose Exit to end the installation process.

Custom Setup Help

From the previous dialog box,

- 1 If you want the IntelliPoint software installed in a directory besides the one specified, choose the Change Directory button.
- 2 Select the components you want to install.

Component	Explanation
Tools & Controls	An application from which you can choose pointer options
Toolbar	A small desktop tool for quick access to key pointer options
MS-DOS Tools & Controls	A version of Tools & Controls that can be run in DOS-mode.
MS-DOS Drivers	Mouse and pointer support for DOS-based applications.
Help	Help files for Tools & Controls and Toolbar
Miscellaneous Files	Other optional drivers

Choose Change Options to select individual files you want installed on your hard disk.

Change Directory Help

► Type the full path of the directory where you want Microsoft IntelliPoint software to be installed.
For example:
C:\SYSTEMMSINPUT

Pointer Options Help

- 1 Select the mouse and pointer options you want to be able to control from IntelliPoint Tools & Controls.

Option	Used to
Special Effects	Select animation options for your pointer
Visibility	Set options to enhance the visibility of your pointer
Clicking	Set Double-Click Speed and enable the ClickSaver option
Orientation	Set pointer direction to match the way you hold your mouse or move the BallPoint Mouse ball
Activity	Set pointer activity options
Appearance	Select pointer shapes
Speed	Set pointer speed options
Buttons	Set primary button, enable both buttons, and assign shortcuts to secondary button and Both Buttons

- 2 Choose OK to continue Setup.

Miscellaneous Options Help

- 1 Select the components you want Setup to install.

Component	Used to
MOUSEPWR.COM	Correct certain problems for laptop computers which, after returning from sleep state, lose mouse support
OS/2 Drivers	Support the mouse and pointer for OS/2 applications

- 2 Choose OK to continue Setup.

