

gmp.info

COLLABORATORS

	<i>TITLE :</i> gmp.info		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		September 19, 2022	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	gmp.info	1
1.1	gmp.info	1
1.2	gmp.info/Copying	2
1.3	gmp.info/Intro	2
1.4	gmp.info/Nomenclature	3
1.5	gmp.info/Thanks	4
1.6	gmp.info/Initialization	4
1.7	gmp.info/Integer Functions	5
1.8	gmp.info/Initializing Integers	6
1.9	gmp.info/Assigning Integers	7
1.10	gmp.info/Simultaneous Integer Init & Assign	8
1.11	gmp.info/Converting Integers	9
1.12	gmp.info/Integer Arithmetic	9
1.13	gmp.info/Logic on Integers	13
1.14	gmp.info/I-O of Integers	13
1.15	gmp.info/Rational Number Functions	14
1.16	gmp.info/Low-level Functions	15
1.17	gmp.info/BSD Compatible Functions	18
1.18	gmp.info/Miscellaneous Functions	19
1.19	gmp.info/Custom Allocation	20
1.20	gmp.info/Reporting Bugs	21
1.21	gmp.info/References	22
1.22	gmp.info/Concept Index	22
1.23	gmp.info/Function Index	23

Chapter 1

gmp.info

1.1 gmp.info

Copying	GMP Copying Conditions.
Intro	Introduction to GMP.
Nomenclature	Terminology and basic data types.
Initialization	Initialization of multi-precision number objects.
Integer Functions	Functions for arithmetic on signed integers.
Rational Number Functions	Functions for arithmetic on rational numbers.
Low-level Functions	Fast functions for natural numbers.
BSD Compatible Functions	All functions found in BSD MP (somewhat faster).
Miscellaneous Functions	Functions that do particular things.
Custom Allocation	How to customize the internal allocation.
Reporting Bugs	Help us to improve this library.
References	
Concept Index	

Function Index

1.2 gmp.info/Copying

GNU MP Copying Conditions

This library is free; this means that everyone is free to use it and free to redistribute it on a free basis. The library is not in the public domain; it is copyrighted and there are restrictions on its distribution, but these restrictions are designed to permit everything that a good cooperating citizen would want to do. What is not allowed is to try to prevent others from further sharing any version of this library that they might get from you.

Specifically, we want to make sure that you have the right to give away copies of the library, that you receive source code or else can get it if you want it, that you can change this library or use pieces of it in new free programs, and that you know you can do these things.

To make sure that everyone has such rights, we have to forbid you to deprive anyone else of these rights. For example, if you distribute copies of the GMP library, you must give the recipients all the rights that you have. You must make sure that they, too, receive or can get the source code. And you must tell them their rights.

Also, for our own protection, we must make certain that everyone finds out that there is no warranty for the GMP library. If it is modified by someone else and passed on, we want their recipients to know that what they have is not what we distributed, so that any problems introduced by others will not reflect on our reputation.

The precise conditions of the license for the GMP library are found in the General Public License that accompany the source code.

1.3 gmp.info/Intro

Introduction to MP

GNU MP is a portable library for arbitrary precision integer and rational number arithmetic.(1) It aims to provide the fastest possible arithmetic for all applications that need more than two words of integer precision.

Most often, applications tend to use just a few words of precision; but some applications may need thousands of words. GNU MP is designed to give good performance for both kinds of applications, by choosing algorithms based on the sizes of the operands.

There are five groups of functions in the MP library:

1. Functions for signed integer arithmetic, with names beginning with `mpz_`.
2. Functions for rational number arithmetic, with names beginning with `mpq_`.
3. Functions compatible with Berkeley MP, such as `itom`, `madd`, and `mult`.
4. Fast low-level functions that operate on natural numbers. These are used by the functions in the preceding groups, and you can also call them directly from very time-critical user programs. These functions' names begin with `mpn_`.
5. Miscellaneous functions.

As a general rule, all MP functions expect output arguments before input arguments. This notation is based on an analogy with the assignment operator. (The BSD MP compatibility functions disobey this rule, having the output argument(s) last.) Multi-precision numbers, whether output or input, are always passed as addresses to the declared type.

Nomenclature

Thanks

----- Footnotes -----

(1) The limit of the precision is set by the available memory in your computer.

1.4 gmp.info/Nomenclature

Nomenclature and Data Types

=====

In this manual, integer means a multiple precision integer, as used in the MP package. The C data type for such integers is `MP_INT`. For example:

```
MP_INT sum;

struct foo { MP_INT x, y; };

MP_INT vec[20];
```

Rational number means a multiple precision fraction. The C data type for these fractions is `MP_RAT`. For example:

MP_RAT quotient;

A limb means the part of a multi-precision number that fits in a single word. (We chose this word because a limb of the human body is analogous to a digit, only larger, and containing several digits.) Normally a limb contains 32 bits.

1.5 gmp.info/Thanks

Thanks

=====

I would like to thank Gunnar Sjoedin and Hans Riesel for their help with mathematical problems, Richard Stallman for his help with design issues and for revising this manual, Brian Beuning and Doug Lea for their testing of various versions of the library, and Joachim Hollman for his many valuable suggestions.

Special thanks to Brian Beuning, he has shaken out many bugs from early versions of the code!

John Amanatides of York University in Canada contributed the function `mpz_probab_prime_p`.

1.6 gmp.info/Initialization

Initialization

Before you can use a variable or object of type `MP_INT` or `MP_RAT`, you must initialize it. This fills in the components that point to dynamically allocated space for the limbs of the number.

When you are finished using the object, you should clear out the object. This frees the dynamic space that it points to, so the space can be used again.

Once you have initialized the object, you need not be concerned about allocating additional space. The functions in the MP package automatically allocate additional space when the object does not already have enough space. They do not, however, reduce the space in use when a smaller number is stored in the object. Most of the time, this policy is best, since it avoids frequent re-allocation. If you want to reduce the space in an object to the minimum needed, you can do `_mpz_realloc (&object, mpz_size (&object))`.

The functions to initialize numbers are `mpz_init` (for `MP_INT`) and `mpq_init` (for `MP_RAT`).

`mpz_init` allocates space for the limbs, and stores a pointer to that space in the `MP_INT` object. It also stores the value 0 in the object.

In the same manner, `mpq_init` allocates space for the numerator and denominator limbs, and stores pointers to these spaces in the `MP_RAT` object.

To clear out a number object, use `mpz_clear` and `mpq_clear`, respectively.

Here is an example of use:

```
{
  MP_INT temp;
  mpz_init (&temp);

  ... store and read values in temp zero or more times ...

  mpz_clear (&temp);
}
```

You might be tempted to copy an integer from one object to another like this:

```
MP_INT x, y;

x = y;
```

Although valid C, this is an error. Rather than copying the integer value from `y` to `x` it will make the two variables share storage. Subsequent assignments to one variable would change the other mysteriously. And if you were to clear out both variables subsequently, you would confuse `malloc` and cause your program to crash.

To copy the value properly, you must use the function `mpz_set`. (see

```
    Assigning Integers
    )
```

1.7 gmp.info/Integer Functions

Integer Functions

This chapter describes the MP functions for performing integer arithmetic.

The integer functions use arguments and values of type `pointer-to-MP_INT` (see

Nomenclature

). The type `MP_INT` is a

structure, but applications should not refer directly to its components. Include the header `gmp.h` to get the definition of `MP_INT`.

Initializing Integers
 Assigning Integers
 Simultaneous Integer Init & Assign
 Converting Integers
 Integer Arithmetic
 Logic on Integers
 I-O of Integers

1.8 gmp.info/Initializing Integers

Initializing Integer Objects

=====

Most of the functions for integer arithmetic assume that the output is stored in an object already initialized. For example, `mpz_add` stores the result of addition (see `Integer Arithmetic`). Thus, you must initialize the object before storing the first value in it. You can do this separately by calling the function `mpz_init`.

- Function: `void mpz_init (MP_INT *integer)`
 Initialize integer with limb space and set the initial numeric value to 0. Each variable should normally only be initialized once, or at least cleared out (using `mpz_clear`) between each initialization.

Here is an example of using `mpz_init`:

```

{
  MP_INT integ;
  mpz_init (&integ);
  ...
  mpz_add (&integ, ...);
  ...
  mpz_sub (&integ, ...);

  /* Unless you are now exiting the program, do ... */
  mpz_clear (&integ);
}

```

As you can see, you can store new values any number of times, once an object is initialized.

- Function: `void mpz_clear (MP_INT *integer)`

Free the limb space occupied by integer. Make sure to call this function for all MP_INT variables when you are done with them.

- Function: void * _mpz_realloc (MP_INT *integer , mp_size new_alloc)
Change the limb space allocation to new_alloc limbs. This function is not normally called from user code, but it can be used to give memory back to the heap, or to increase the space of a variable to avoid repeated automatic re-allocation.
- Function: void mpz_array_init (MP_INT integer_array [], size_t array_size , mp_size fixed_num_limbs)
Allocate fixed limb space for all array_size integers in integer_array. The fixed allocation for each integer in the array is fixed_num_limbs. This function is useful for decreasing the working set for some algorithms that use large integer arrays. If the fixed space will be insufficient for storing the result of a subsequent calculation, the result is unpredictable.

There is no way to de-allocate the storage allocated by this function. Don't call mpz_clear!

1.9 gmp.info/Assigning Integers

Integer Assignment Functions

These functions assign new values to already initialized integers (see

Initializing Integers
) .

- Function: void mpz_set (MP_INT *dest_integer , MP_INT *src_integer)
Assign dest_integer from src_integer.
- Function: void mpz_set_ui (MP_INT *integer , unsigned long int initial_value)
Set the value of integer from initial_value.
- Function: void mpz_set_si (MP_INT *integer , signed long int initial_value)
Set the value of integer from initial_value.
- Function: int mpz_set_str (MP_INT *integer , char *initial_value , int base)
Set the value of integer from initial_value, a '\0'-terminated C string in base base. White space is allowed in the string, and is simply ignored. The base may vary from 2 to 36. If base is 0, the actual base is determined from the leading characters: if the first two characters are '0x' or '0X', hexadecimal is assumed, otherwise if the first character is '0', octal is assumed, otherwise decimal is assumed.

This function returns 0 if the entire string up to the '\0' is a

valid number in base base. Otherwise it returns -1.

1.10 gmp.info/Simultaneous Integer Init & Assign

Combined Initialization and Assignment Functions

For your convenience, MP provides a parallel series of initialize-and-set arithmetic functions which initialize the output and then store the value there. These functions' names have the form `mpz_init_set....`

Here is an example of using one:

```
{
  MP_INT integ;
  mpz_init_set_str (&integ, "3141592653589793238462643383279502884", 10);
  ...
  mpz_sub (&integ, ...);

  mpz_clear (&integ);
}
```

Once the integer has been initialized by any of the `mpz_init_set...` functions, it can be used as the source or destination operand for the ordinary integer functions. Don't use an initialize-and-set function on a variable already initialized!

- Function: `void mpz_init_set (MP_INT *dest_integer , MP_INT *src_integer)`
Initialize `dest_integer` with limb space and set the initial numeric value from `src_integer`.
- Function: `void mpz_init_set_ui (MP_INT *dest_integer , unsigned long int src_ulong)`
Initialize `dest_integer` with limb space and set the initial numeric value from `src_ulong`.
- Function: `void mpz_init_set_si (MP_INT *dest_integer , signed long int src_slong)`
Initialize `dest_integer` with limb space and set the initial numeric value from `src_slong`.
- Function: `int mpz_init_set_str (MP_INT *dest_integer , char *src_cstring , int base)`
Initialize `dest_integer` with limb space and set the initial numeric value from `src_cstring`, a '\0'-terminated C string in base `base`. The base may vary from 2 to 36. There may be white space in the string.

If the string is a correct base `base` number, the function returns 0; if an error occurs it returns -1. `dest_integer` is initialized even if an error occurs. (I.e., you have to call `mpz_clear` for

it.)

1.11 gmp.info/Converting Integers

Conversion Functions

=====

- Function: unsigned long int mpz_get_ui (MP_INT *src_integer)
Return the least significant limb from src_integer. This function together with
mpz_div_2exp(..., src_integer, CHAR_BIT*sizeof(unsigned long int))
can be used to extract the limbs of an integer efficiently.
- Function: signed long int mpz_get_si (MP_INT *src_integer)
If src_integer fits into a signed long int return the value of src_integer. Otherwise return the least significant bits of src_integer, with the same sign as src_integer.
- Function: char * mpz_get_str (char *string , int base , MP_INT *integer)
Convert integer to a '\0'-terminated C string in string, using base base. The base may vary from 2 to 36. If string is NULL, space for the string is allocated using the default allocation function.

If string is not NULL, it should point to a block of storage enough large for the result. To find out the right amount of space to provide for string, use mpz_sizeinbase (integer, base) + 2. The "+ 2" is for a possible minus sign, and for the terminating null character. (see
Miscellaneous Functions
).

This function returns a pointer to the result string.

1.12 gmp.info/Integer Arithmetic

Integer Arithmetic Functions

=====

- Function: void mpz_add (MP_INT *sum , MP_INT *addend1 , MP_INT *addend2)
- Function: void mpz_add_ui (MP_INT *sum , MP_INT *addend1 , unsigned long int addend2)
Set sum to addend1 + addend2.
- Function: void mpz_sub (MP_INT *difference , MP_INT *minuend , MP_INT *subtrahend)

- Function: void mpz_sub_ui (MP_INT *difference , MP_INT *minuend , unsigned long int subtrahend)
Set difference to minuend - subtrahend.
- Function: void mpz_mul (MP_INT *product , MP_INT *multiplier , MP_INT *multiplicand)
- Function: void mpz_mul_ui (MP_INT *product , MP_INT *multiplier , unsigned long int multiplicand)
Set product to multiplier times multiplicand.

Division is undefined if the divisor is zero, and passing a zero divisor to the divide or modulo functions, as well passing a zero mod argument to the powm functions, will make these functions intentionally divide by zero. This gives the user the possibility to handle arithmetic exceptions in these functions in the same manner as other arithmetic exceptions.

- Function: void mpz_div (MP_INT *quotient , MP_INT *dividend , MP_INT *divisor)
- Function: void mpz_div_ui (MP_INT *quotient , MP_INT *dividend , unsigned long int divisor)
Set quotient to dividend / divisor. The quotient is rounded towards 0.
- Function: void mpz_mod (MP_INT *remainder , MP_INT *dividend , MP_INT *divisor)
- Function: void mpz_mod_ui (MP_INT *remainder , MP_INT *dividend , unsigned long int divisor)
Divide dividend and divisor and put the remainder in remainder. The remainder has the same sign as the dividend, and its absolute value is less than the absolute value of the divisor.
- Function: void mpz_divmod (MP_INT *quotient , MP_INT *remainder , MP_INT *dividend , MP_INT *divisor)
- Function: void mpz_divmod_ui (MP_INT *quotient , MP_INT *remainder , MP_INT *dividend , unsigned long int divisor)
Divide dividend and divisor and put the quotient in quotient and the remainder in remainder. The quotient is rounded towards 0. The remainder has the same sign as the dividend, and its absolute value is less than the absolute value of the divisor.

If quotient and remainder are the same variable, the results are not defined.

- Function: void mpz_mdiv (MP_INT *quotient , MP_INT *dividend , MP_INT *divisor)
 - Function: void mpz_mdiv_ui (MP_INT *quotient , MP_INT *dividend , unsigned long int divisor)
Set quotient to dividend / divisor. The quotient is rounded towards -infinity.
-

- Function: void mpz_mmod (MP_INT *remainder , MP_INT *divdend , MP_INT *divisor)

 - Function: unsigned long int mpz_mmod_ui (MP_INT *remainder , MP_INT *divdend , unsigned long int divisor)
Divide dividend and divisor and put the remainder in remainder. The remainder is always positive, and its value is less than the value of the divisor.

For mpz_mmod_ui the remainder is returned, and if remainder is not NULL, also stored there.

 - Function: void mpz_mdivmod (MP_INT *quotient , MP_INT *remainder , MP_INT *dividend , MP_INT *divisor)

 - Function: unsigned long int mpz_mdivmod_ui (MP_INT *quotient , MP_INT *remainder , MP_INT *dividend , unsigned long int divisor)
Divide dividend and divisor and put the quotient in quotient and the remainder in remainder. The quotient is rounded towards -infinity. The remainder is always positive, and its value is less than the value of the divisor.

For mpz_mdivmod_ui the remainder is small enough to fit in an unsigned long int, and is therefore returned. If remainder is not NULL, the remainder is also stored there.

If quotient and remainder are the same variable, the results are not defined.

 - Function: void mpz_sqrt (MP_INT *root , MP_INT *operand)
Set root to the square root of operand. The result is rounded towards zero.

 - Function: void mpz_sqrtrem (MP_INT *root , MP_INT *remainder , MP_INT *operand)
Set root to the square root of operand, as with mpz_sqrt. Set remainder to operand -root*root, (i.e. zero if operand is a perfect square).

If root and remainder are the same variable, the results are not defined.

 - Function: int mpz_perfect_square_p (MP_INT *square)
Return non-zero if square is perfect, i.e. if the square root of square is integral. Return zero otherwise.

 - Function: int mpz_probab_prime_p (MP_INT *n , int reps)
An implementation of the probabilistic primality test found in Knuth's Seminumerical Algorithms book. If the function mpz_probab_prime_p(n, reps) returns 0 then n is not prime. If it returns 1, then n is 'probably' prime. The probability of a false positive is (1/4)**reps, where reps is the number of internal passes of the probabilistic algorithm. Knuth indicates that 25 passes are reasonable.

 - Function: void mpz_powm (MP_INT *res , MP_INT *base , MP_INT *exp ,
-

- MP_INT *mod)
- Function: void mpz_powm_ui (MP_INT *res , MP_INT *base , unsigned long int exp , MP_INT *mod)
Set res to (base raised to exp) modulo mod. If exp is negative, the result is undefined.
 - Function: void mpz_pow_ui (MP_INT *res , MP_INT *base , unsigned long int exp)
Set res to base raised to exp.
 - Function: void mpz_fac_ui (MP_INT *res , unsigned long int n)
Set res n!, the factorial of n.
 - Function: void mpz_gcd (MP_INT *res , MP_INT *operand1 , MP_INT *operand2)
Set res to the greatest common divisor of operand1 and operand2.
 - Function: void mpz_gcdext (MP_INT *g , MP_INT *s , MP_INT *t , MP_INT *a , MP_INT *b)
Compute g, s, and t, such that $a s + b t = g = \text{gcd}(a, b)$. If t is NULL, that argument is not computed.
 - Function: void mpz_neg (MP_INT *negated_operand , MP_INT *operand)
Set negated_operand to -operand.
 - Function: void mpz_abs (MP_INT *positive_operand , MP_INT *signed_operand)
Set positive_operand to the absolute value of signed_operand.
 - Function: int mpz_cmp (MP_INT *operand1 , MP_INT *operand2)
 - Function: int mpz_cmp_ui (MP_INT *operand1 , unsigned long int operand2)
 - Function: int mpz_cmp_si (MP_INT *operand1 , signed long int operand2)
Compare operand1 and operand2. Return a positive value if operand1 > operand2, zero if operand1 = operand2, and a negative value if operand1 < operand2.
 - Function: void mpz_mul_2exp (MP_INT *product , MP_INT *multiplier , unsigned long int exponent_of_2)
Set product to multiplier times 2 raised to exponent_of_2. This operation can also be defined as a left shift, exponent_of_2 steps.
 - Function: void mpz_div_2exp (MP_INT *quotient , MP_INT *dividend , unsigned long int exponent_of_2)
Set quotient to dividend divided by 2 raised to exponent_of_2. This operation can also be defined as a right shift, exponent_of_2 steps, but unlike the >> operator in C, the result is rounded towards 0.
 - Function: void mpz_mod_2exp (MP_INT *remainder , MP_INT *dividend , unsigned long int exponent_of_2)
Set remainder to dividend mod (2 raised to exponent_of_2). The
-

sign of remainder will have the same sign as dividend.

This operation can also be defined as a masking of the exponent_of_2 least significant bits.

1.13 gmp.info/Logic on Integers

Logical Functions

=====

- Function: void mpz_and (MP_INT *conjunction , MP_INT *operand1 , MP_INT *operand2)
Set conjunction to operand1 logical-and operand2.

- Function: void mpz_ior (MP_INT *disjunction , MP_INT *operand1 , MP_INT *operand2)
Set disjunction to operand1 inclusive-or operand2.

- Function: void mpz_xor (MP_INT *disjunction , MP_INT *operand1 , MP_INT *operand2)
Set disjunction to operand1 exclusive-or operand2.

This function is missing in the current release.

- Function: void mpz_com (MP_INT *complemented_operand , MP_INT *operand)
Set complemented_operand to the one's complement of operand.

1.14 gmp.info/I-O of Integers

Input and Output Functions

=====

Functions that perform input from a standard I/O stream, and functions for output conversion.

- Function: void mpz_inp_raw (MP_INT *integer , FILE *stream)
Input from standard I/O stream stream in the format written by mpz_out_raw, and put the result in integer.

- Function: void mpz_inp_str (MP_INT *integer , FILE *stream , int base)
Input a string in base base from standard I/O stream stream, and put the read integer in integer. The base may vary from 2 to 36. If base is 0, the actual base is determined from the leading characters: if the first two characters are '0x' or '0X', hexadecimal is assumed, otherwise if the first character is '0', octal is assumed, otherwise decimal is assumed.

- Function: void mpz_out_raw (FILE *stream , MP_INT *integer)

Output integer on standard I/O stream stream, in raw binary format. The integer is written in a portable format, with 4 bytes of size information, and that many bytes of limbs. Both the size and the limbs are written in decreasing significance order.

- Function: void mpz_out_str (FILE *stream , int base , MP_INT *integer)
Output integer on standard I/O stream stream, as a string of digits in base base. The base may vary from 2 to 36.

1.15 gmp.info/Rational Number Functions

Rational Number Functions

All rational arithmetic functions canonicalize the result, so that the denominator and the numerator have no common factors. Zero has the unique representation 0/1.

The set of functions is quite small. Maybe it will be extended in a future release.

- Function: void mpq_init (MP_RAT *dest_rational)
Initialize dest_rational with limb space and set the initial numeric value to 0/1. Each variable should normally only be initialized once, or at least cleared out (using the function mpq_clear) between each initialization.
- Function: void mpq_clear (MP_RAT *rational_number)
Free the limb space occupied by rational_number. Make sure to call this function for all MP_RAT variables when you are done with them.
- Function: void mpq_set (MP_RAT *dest_rational , MP_RAT *src_rational)
Assign dest_rational from src_rational.
- Function: void mpq_set_ui (MP_RAT *rational_number , unsigned long int numerator , unsigned long int denominator)
Set the value of rational_number to numerator/denominator. If numerator and denominator have common factors, they are divided out before rational_number is assigned.
- Function: void mpq_set_si (MP_RAT *rational_number , signed long int numerator , unsigned long int denominator)
Like mpq_set_ui, but numerator is signed.
- Function: void mpq_add (MP_RAT *sum , MP_RAT *addend1 , MP_RAT *addend2)
Set sum to addend1 + addend2.
- Function: void mpq_sub (MP_RAT *difference , MP_RAT *minuend , MP_RAT *subtrahend)
Set difference to minuend - subtrahend.

- Function: void mpq_mul (MP_RAT *product , MP_RAT *multiplier , MP_RAT *multiplicand)
Set product to multiplier * multiplicand
- Function: void mpq_div (MP_RAT *quotient , MP_RAT *dividend , MP_RAT *divisor)
Set quotient to dividend / divisor.
- Function: void mpq_neg (MP_RAT *negated_operand , MP_RAT *operand)
Set negated_operand to -operand.
- Function: int mpq_cmp (MP_RAT *operand1 , MP_RAT *operand2)
Compare operand1 and operand2. Return a positive value if operand1 > operand2, zero if operand1 = operand2, and a negative value if operand1 < operand2.
- Function: void mpq_inv (MP_RAT *inverted_number , MP_RAT *number)
Invert number by swapping the numerator and denominator. If the new denominator becomes zero, this routine will divide by zero.
- Function: void mpq_set_num (MP_RAT *rational_number , MP_INT *numerator)
Make numerator become the numerator of rational_number by copying.
- Function: void mpq_set_den (MP_RAT *rational_number , MP_INT *denominator)
Make denominator become the denominator of rational_number by copying. If denominator < 0 the denominator of rational_number is set to the absolute value of denominator, and the sign of the numerator of rational_number is changed.
- Function: void mpq_get_num (MP_INT *numerator , MP_RAT *rational_number)
Copy the numerator of rational_number to the integer numerator, to prepare for integer operations on the numerator.
- Function: void mpq_get_den (MP_INT *denominator , MP_RAT *rational_number)
Copy the denominator of rational_number to the integer denominator, to prepare for integer operations on the denominator.

1.16 gmp.info/Low-level Functions

Low-level Functions

The next release of the GNU MP library (2.0) will include changes to some mpn functions. Programs that use these functions according to the descriptions below will therefore not work with the next release.

The low-level function layer is designed to be as fast as possible, not to provide a coherent calling interface. The different functions

have similar interfaces, but there are variations that might be confusing. These functions do as little as possible apart from the real multiple precision computation, so that no time is spent on things that not all callers need.

A source operand is specified by a pointer to the least significant limb and a limb count. A destination operand is specified by just a pointer. It is the responsibility of the caller to ensure that the destination has enough space for storing the result.

With this way of specifying source operands, it is possible to perform computations on subranges of an argument, and store the result into a subrange of a destination.

All these functions require that the operands are normalized in the sense that the most significant limb must be non-zero. (A future release of might drop this requirement.)

The low-level layer is the base for the implementation of the `mpz_` and `mpq_` layers.

The code below adds the number beginning at `src1_ptr` and the number beginning at `src2_ptr` and writes the sum at `dest_ptr`. A constraint for `mpn_add` is that `src1_size` must not be smaller than `src2_size`.

```
mpn_add (dest_ptr, src1_ptr, src1_size, src2_ptr, src2_size)
```

In the description below, a source operand is identified by the pointer to the least significant limb, and the limb count in braces.

- Function: `mp_size mpn_add (mp_ptr dest_ptr , mp_srcptr src1_ptr , mp_size src1_size , mp_srcptr src2_ptr , mp_size src2_size)`
Add {`src1_ptr`, `src1_size` } and {`src2_ptr`, `src2_size` }, and write the `src1_size` least significant limbs of the result to `dest_ptr`. Carry-out, either 0 or 1, is returned.

This function requires that `src1_size` is greater than or equal to `src2_size`.

- Function: `mp_size mpn_sub (mp_ptr dest_ptr , mp_srcptr src1_ptr , mp_size src1_size , mp_srcptr src2_ptr , mp_size src2_size)`
Subtract {`src2_ptr`, `src2_size` } from {`src1_ptr`, `src1_size` }, and write the result to `dest_ptr`.

Return 1 if the minuend < the subtrahend. Otherwise, return the negative difference between the number of words in the result and the minuend. I.e. return 0 if the result has `src1_size` words, -1 if it has `src1_size - 1` words, etc.

This function requires that `src1_size` is greater than or equal to `src2_size`.

- Function: `mp_size mpn_mul (mp_ptr dest_ptr , mp_srcptr src1_ptr , mp_size src1_size , mp_srcptr src2_ptr , mp_size src2_size)`
Multiply {`src1_ptr`, `src1_size` } and {`src2_ptr`, `src2_size` }, and write the result to `dest_ptr`. The exact size of the result is returned.

The destination has to have space for `src1_size + src1_size` limbs, even if the result might be one limb smaller.

This function requires that `src1_size` is greater than or equal to `src2_size`. The destination must be distinct from either input operands.

- Function: `mp_size mpn_div (mp_ptr dest_ptr , mp_ptr src1_ptr , mp_size src1_size , mp_srcptr src2_ptr , mp_size src2_size)`
Divide `{src1_ptr, src1_size }` by `{src2_ptr, src2_size }`, and write the quotient to `dest_ptr`, and the remainder to `src1_ptr`.

Return 0 if the quotient size is at most `(src1_size - src2_size)`, and 1 if the quotient size is at most `(src1_size - src2_size + 1)`. The caller has to check the most significant limb to find out the exact size.

The most significant bit of the most significant limb of the divisor has to be set.

This function requires that `src1_size` is greater than or equal to `src2_size`. The quotient, pointed to by `dest_ptr`, must be distinct from either input operands.

- Function: `mp_limb mpn_lshift (mp_ptr dest_ptr , mp_srcptr src_ptr , mp_size src_size , unsigned long int count)`
Shift `{src_ptr, src_size }` count bits to the left, and write the `src_size` least significant limbs of the result to `dest_ptr`. count might be in the range 1 to `n - 1`, on an `n`-bit machine. The limb shifted out is returned.

Overlapping of the destination space and the source space is allowed in this function, provided `dest_ptr >= src_ptr`.

- Function: `mp_size mpn_rshift (mp_ptr dest_ptr , mp_srcptr src_ptr , mp_size src_size , unsigned long int count)`
Shift `{src_ptr, src_size }` count bits to the right, and write the `src_size` least significant limbs of the result to `dest_ptr`. count might be in the range 1 to `n - 1`, on an `n`-bit machine. The size of the result is returned.

Overlapping of the destination space and the source space is allowed in this function, provided `dest_ptr <= src_ptr`.

- Function: `mp_size mpn_rshiftci (mp_ptr dest_ptr , mp_srcptr src_ptr , mp_size src_size , unsigned long int count , mp_limb inlimb)`
Like `mpn_rshift`, but use `inlimb` to feed the least significant end of the destination.

- Function: `int mpn_cmp (mp_srcptr src1_ptr , mp_srcptr src2_ptr , mp_size size)`
Compare `{src1_ptr, size }` and `{src2_ptr, size }` and return a positive value if `src1 > src2`, 0 if they are equal, and a negative value if `src1 < src2`.

1.17 gmp.info/BSD Compatible Functions

Berkeley MP Compatible Functions

These functions are intended to be fully compatible with the Berkeley MP library which is available on many BSD derived U*xix systems.

The original Berkeley MP library has a usage restriction: you cannot use the same variable as both source and destination in a single function call. The compatible functions in GNU MP do not share this restriction--inputs and outputs may overlap.

It is not recommended that new programs are written using these functions. Apart from the incomplete set of functions, the interface for initializing MINT objects is more error prone, and the pow function collides with pow in libm.a.

Include the header mp.h to get the definition of the necessary types and functions. If you are on a BSD derived system, make sure to include GNU mp.h if you are going to link the GNU libmp.a to your program. This means that you probably need to give the `-I<dir>` option to the compiler, where `<dir>` is the directory where you have GNU mp.h.

- Function: `MINT * itom (signed short int initial_value)`
Allocate an integer consisting of a MINT object and dynamic limb space. Initialize the integer to `initial_value`. Return a pointer to the MINT object.
 - Function: `MINT * xtom (char *initial_value)`
Allocate an integer consisting of a MINT object and dynamic limb space. Initialize the integer from `initial_value`, a hexadecimal, `'\0'`-terminate C string. Return a pointer to the MINT object.
 - Function: `void move (MINT *src , MINT *dest)`
Set `dest` to `src` by copying. Both variables must be previously initialized.
 - Function: `void madd (MINT *src_1 , MINT *src_2 , MINT *destination)`
Add `src_1` and `src_2` and put the sum in `destination`.
 - Function: `void msub (MINT *src_1 , MINT *src_2 , MINT *destination)`
Subtract `src_2` from `src_1` and put the difference in `destination`.
 - Function: `void mult (MINT *src_1 , MINT *src_2 , MINT *destination)`
Multiply `src_1` and `src_2` and put the product in `destination`.
 - Function: `void mdiv (MINT *dividend , MINT *divisor , MINT *quotient , MINT *remainder)`
 - Function: `void sdiv (MINT *dividend , signed short int divisor , MINT *quotient , signed short int *remainder)`
Set `quotient` to `dividend / divisor`, and `remainder` to `dividend mod`
-

divisor. The quotient is rounded towards zero; the remainder has the same sign as the dividend.

Some implementations of this function return a remainder whose sign is inverted if the divisor is negative. Such a definition makes little sense from a mathematical point of view. GNU MP might be considered incompatible with the traditional MP in this respect.

- Function: void msqrt (MINT *operand , MINT *root , MINT *remainder)
Set root to the square root of operand, as with mpz_sqrt. Set remainder to operand-root*root, (i.e. zero if operand is a perfect square).
- Function: void pow (MINT *base , MINT *exp , MINT *mod , MINT *dest)
Set dest to (base raised to exp) modulo mod.
- Function: void rpow (MINT *base , signed short int exp , MINT *dest)
Set dest to base raised to exp.
- Function: void gcd (MINT *operand1 , MINT *operand2 , MINT *res)
Set res to the greatest common divisor of operand1 and operand2.
- Function: int mcmp (MINT *operand1 , MINT *operand2)
Compare operand1 and operand2. Return a positive value if operand1 > operand2, zero if operand1 = operand2, and a negative value if operand1 < operand2.
- Function: void min (MINT *dest)
Input a decimal string from stdin, and put the read integer in dest. SPC and TAB are allowed in the number string, and are ignored.
- Function: void mout (MINT *src)
Output src to stdout, as a decimal string. Also output a newline.
- Function: char * mtox (MINT *operand)
Convert operand to a hexadecimal string, and return a pointer to the string. The returned string is allocated using the default memory allocation function, malloc by default. (See Initialization
,
for an explanation of the memory allocation in MP).
- Function: void mfree (MINT *operand)
De-allocate, the space used by operand. This function should only be passed a value returned by itom or xtom.

1.18 gmp.info/Miscellaneous Functions

Miscellaneous Functions

- Function: void mpz_random (MP_INT *random_integer , mp_size max_size)
Generate a random integer of at most max_size limbs. The generated random number doesn't satisfy any particular requirements of randomness.
- Function: void mpz_random2 (MP_INT *random_integer , mp_size max_size)
Generate a random integer of at most max_size limbs, with long strings of zeros and ones in the binary representation. Useful for testing functions and algorithms, since this kind of random numbers have proven to be more likely to trigger bugs.
- Function: size_t mpz_size (MP_INT *integer)
Return the size of integer measured in number of limbs. If integer is zero, the returned value will be zero, if integer has one limb, the returned value will be one, etc. (See Nomenclature , for an explanation of the concept limb.)
- Function: size_t mpz_sizeinbase (MP_INT *integer , int base)
Return the size of integer measured in number of digits in base base. The base may vary from 2 to 36. The returned value will be exact or 1 too big. If base is a power of 2, the returned value will always be exact.

This function is useful in order to allocate the right amount of space before converting integer to a string. The right amount of allocation is normally two more than the value returned by mpz_sizeinbase (one extra for a minus sign and one for the terminating '\0').

1.19 gmp.info/Custom Allocation

Custom Allocation

=====

By default, the initialization functions use malloc, realloc, and free to do their work. If malloc or realloc fails, the MP package terminates execution after a printing fatal error message on standard error.

In some applications, you may wish to allocate memory in other ways, or you may not want to have a fatal error when there is no more memory available. To accomplish this, you can specify alternative functions for allocating and de-allocating memory. Use mp_set_memory_functions to do this.

mp_set_memory_functions has three arguments, allocate_function, reallocate_function, and deallocate_function, in that order. If an argument is NULL, the corresponding default function is retained.

The functions you supply should fit the following declarations:

```
void * allocate_function (size_t alloc_size)
```

This function should return a pointer to newly allocated space with at least `alloc_size` storage units.

```
void * reallocate_function (void *ptr, size_t old_size, size_t new_size)
```

This function should return a pointer to newly allocated space of at least `new_size` storage units, after copying the first `old_size` storage units from `ptr`. It should also de-allocate the space at `ptr`.

You can assume that the space at `ptr` was formerly returned from `allocate_function` or `reallocate_function`, for a request for `old_size` storage units.

```
void deallocate_function (void *ptr, size_t size)
```

De-allocate the space pointed to by `ptr`.

You can assume that the space at `ptr` was formerly returned from `allocate_function` or `reallocate_function`, for a request for `size` storage units.

(A storage unit is the unit in which the `sizeof` operator returns the size of an object, normally an 8 bit byte.)

NOTE: call `mp_set_memory_functions` only before calling any other MP functions. Otherwise, the user-defined allocation functions may be asked to re-allocate or de-allocate something previously allocated by the default allocation functions.

1.20 gmp.info/Reporting Bugs

Reporting Bugs

If you think you have found a bug in the GNU MP library, please investigate it and report it. We have made this library available to you, and it is not to ask too much from you, to ask you to report the bugs that you find.

Please make sure that the bug is really in the GNU MP library.

You have to send us a test case that makes it possible for us to reproduce the bug.

You also have to explain what is wrong; if you get a crash, or if the results printed are not good and in that case, in what way.

Make sure that the bug report includes all information you would need to fix this kind of bug for someone else. Think twice.

If your bug report is good, we will do our best to help you to get a corrected version of the library; if the bug report is poor, we won't do

anything about it (aside of chiding you to send better bug reports).

Send your bug report to: tege@gnu.ai.mit.edu.

If you think something in this manual is unclear, or downright incorrect, or if the language needs to be improved, please send a note to the same address.

1.21 gmp.info/References

References

- * Donald E. Knuth, "The Art of Computer Programming", vol 2, "Seminumerical Algorithms", 2nd edition, Addison-Wesley, 1981.
- * John D. Lipson, "Elements of Algebra and Algebraic Computing", The Benjamin Cummins Publishing Company Inc, 1981.
- * Richard M. Stallman, "Using and Porting GCC", Free Software Foundation, 1993.
- * Peter L. Montgomery, "Modular Multiplication Without Trial Division", Mathematics of Computation, volume 44, number 170, April 1985.

1.22 gmp.info/Concept Index

Concept Index

```

Arithmetic functions
    Integer Arithmetic

BSD MP compatible functions
    BSD Compatible Functions

Conditions for copying GNU MP
    Copying

Conversion functions
    Converting Integers

Copying conditions
    Copying

I/O functions
    I-O of Integers

```

Initialization and assignment functions, combined
Simultaneous Integer Init & Assign

Input and output functions
I-O of Integers

integer
Nomenclature

Integer arithmetic functions
Integer Arithmetic

Integer assignment functions
Assigning Integers

Integer functions
Integer Functions

Introduction
Intro

limb
Nomenclature

Logical functions
Logic on Integers

Low-level functions
Low-level Functions

Miscellaneous functions
Miscellaneous Functions

nomenclature
Nomenclature

Output functions
I-O of Integers

Overview
Intro

rational number
Nomenclature

Rational number functions
Rational Number Functions

Reporting bugs
Reporting Bugs

1.23 gmp.info/Function Index

Function and Type Index

MP_INT	Nomenclature
MP_RAT	Nomenclature
gcd	BSD Compatible Functions
itom	BSD Compatible Functions
madd	BSD Compatible Functions
ncmp	BSD Compatible Functions
mdiv	BSD Compatible Functions
mfree	BSD Compatible Functions
min	BSD Compatible Functions
mout	BSD Compatible Functions
move	BSD Compatible Functions
mpn_add	Low-level Functions
mpn_cmp	Low-level Functions
mpn_div	Low-level Functions
mpn_lshift	Low-level Functions
mpn_mul	Low-level Functions
mpn_rshift	Low-level Functions

mpn_rshiftci	Low-level Functions
mpn_sub	Low-level Functions
mpq_add	Rational Number Functions
mpq_clear	Rational Number Functions
mpq_cmp	Rational Number Functions
mpq_div	Rational Number Functions
mpq_get_den	Rational Number Functions
mpq_get_num	Rational Number Functions
mpq_init	Rational Number Functions
mpq_inv	Rational Number Functions
mpq_mul	Rational Number Functions
mpq_neg	Rational Number Functions
mpq_set	Rational Number Functions
mpq_set_den	Rational Number Functions
mpq_set_num	Rational Number Functions
mpq_set_si	Rational Number Functions
mpq_set_ui	Rational Number Functions
mpq_sub	Rational Number Functions
mpz_abs	Integer Arithmetic

mpz_add	Integer Arithmetic
mpz_add_ui	Integer Arithmetic
mpz_and	Logic on Integers
mpz_array_init	Initializing Integers
mpz_clear	Initializing Integers
mpz_cmp	Integer Arithmetic
mpz_cmp_si	Integer Arithmetic
mpz_cmp_ui	Integer Arithmetic
mpz_com	Logic on Integers
mpz_div	Integer Arithmetic
mpz_divmod	Integer Arithmetic
mpz_divmod_ui	Integer Arithmetic
mpz_div_2exp	Integer Arithmetic
mpz_div_ui	Integer Arithmetic
mpz_fac_ui	Integer Arithmetic
mpz_gcd	Integer Arithmetic
mpz_gcdext	Integer Arithmetic
mpz_get_si	Converting Integers
mpz_get_str	Converting Integers

mpz_get_ui	Converting Integers
mpz_init	Initializing Integers
mpz_init_set	Simultaneous Integer Init & Assign
mpz_init_set_si	Simultaneous Integer Init & Assign
mpz_init_set_str	Simultaneous Integer Init & Assign
mpz_init_set_ui	Simultaneous Integer Init & Assign
mpz_inp_raw	I-O of Integers
mpz_inp_str	I-O of Integers
mpz_ior	Logic on Integers
mpz_mdiv	Integer Arithmetic
mpz_mdivmod	Integer Arithmetic
mpz_mdivmod_ui	Integer Arithmetic
mpz_mdiv_ui	Integer Arithmetic
mpz_mmod	Integer Arithmetic
mpz_mmod_ui	Integer Arithmetic
mpz_mod	Integer Arithmetic
mpz_mod_2exp	Integer Arithmetic
mpz_mod_ui	Integer Arithmetic
mpz_mul	Integer Arithmetic

mpz_mul_2exp	Integer Arithmetic
mpz_mul_ui	Integer Arithmetic
mpz_neg	Integer Arithmetic
mpz_out_raw	I-O of Integers
mpz_out_str	I-O of Integers
mpz_perfect_square_p	Integer Arithmetic
mpz_powm	Integer Arithmetic
mpz_powm_ui	Integer Arithmetic
mpz_pow_ui	Integer Arithmetic
mpz_probab_prime_p	Integer Arithmetic
mpz_random	Miscellaneous Functions
mpz_random2	Miscellaneous Functions
mpz_set	Assigning Integers
mpz_set_si	Assigning Integers
mpz_set_str	Assigning Integers
mpz_set_ui	Assigning Integers
mpz_size	Miscellaneous Functions
mpz_sizeinbase	Miscellaneous Functions
mpz_sqrt	Integer Arithmetic

mpz_sqrtrem	Integer Arithmetic
mpz_sub	Integer Arithmetic
mpz_sub_ui	Integer Arithmetic
mpz_xor	Logic on Integers
mp_set_memory_functions	Custom Allocation
msqrt	BSD Compatible Functions
msub	BSD Compatible Functions
mtox	BSD Compatible Functions
mult	BSD Compatible Functions
pow	BSD Compatible Functions
rpow	BSD Compatible Functions
sdiv	BSD Compatible Functions
xtom	BSD Compatible Functions
_mpz_realloc	Initializing Integers
