

# WCL Help

WCL is a command line processor for Microsoft Windows 3.1, and IBM Win-OS/2. There are several internal commands available in WCL under the headings listed below. A proper introduction to WCL is contained within the "Introduction" section below. If you are new to WCL please read that section first.

**REGISTRATION FEE: £18.00 (U.K. Sterling; or see the "REGISTRATION" section below for the fee if paid in other currencies)**

**Many thanks to those who have registered WCL. If you have not registered your copy, please consider doing so;**

**Please send registration requests to:**

**Dr. A. Olowofoyeku,  
268 Horwood, Newcastle,  
Staffordshire, ST5 5BQ, ENGLAND.  
E-mail: laa12@keele.ac.uk (Internet)**

**If you are not in the U.K., please see the REGISTRATION SITES section below for your local registration site.**

[Introduction](#)  
[Alphabetical List](#)  
[Directory Services](#)  
[File Services](#)  
[System Services](#)  
[Miscellaneous Services](#)  
[Command Line History](#)  
[Batch Files](#)  
[INI File Settings](#)  
[Disclaimer](#)  
[Registration](#)  
[Registration Sites](#)  
[Registration FORM](#)

# Alphabetical List of Commands

Below is an alphabetical list of internal commands supported by WCL. They can all be found grouped under the various services listed in the index screen.

!  
!!  
?  
??  
ABOUT  
ADD  
ALIAS  
ATTRIB  
BACKINI  
BACKUPTHEINIS  
BEEP  
CD  
CHANGE  
CHG2  
CLS  
COLOR  
COMMAND ALIASES  
CLEAR  
COPY  
COPYTREE  
DATE  
DEL  
DELTREE  
DIR  
DQ  
DOS  
DOSKEY  
EXIT  
FREE  
GETCOLOR  
GOTO  
HALT  
H  
HOME  
H2  
HELP  
HELP2  
HIDE  
KILLPROG  
LIST  
LISTCOMMANDS  
LISTWINS  
MD  
NEWCOMMAND  
PATH  
PLAY  
PRINT  
PROMPT  
PWD

RD  
REN  
RENAMEWIN  
RESTART  
REVEAL  
SAVE  
SAY  
SEEK  
SET  
SETDATE  
SETTIME  
SPAWN  
SUM  
SYSDIR  
TIME  
TYPE  
TYPEWRITE  
UPDATE  
WINDIR  
WINLOAD  
WINRUN  
WINSHELL

## Directory Services

WCL supports a number of internal commands for directory services. The supported internal commands operate similarly to the DOS equivalents. Sometimes however, there may be minor variations. The directory commands are outlined below

ALIAS

CD

DIR

GOTO

HOME

MD

PWD

RD

## DIR

List the files in the directory. This can take parameters. e.g "DIR A:\\*.EXE", "DIR C:\MSDOS", etc. If no parameter is supplied, then there will be a listing of the CURRENT directory. The list displays about 20 lines and then pauses for a key press - much like "DIR/P" in DOS.) By default, the directory listing is sorted, according to the names of the files, with sub-directories appearing first before files. You can afterward scroll up and down the file list window with the mouse, or by using the PgUp, PgDn, and arrow keys.

The DIR command takes other parameters to change the order of sorting, or the format of the file listing. To see the options available here, type "DIR /?" (note that there must be a space between the "DIR" and the "/" parameter).

The Directory listing is sorted, with sub-directories appearing first before files. You can afterward scroll up and down the file list window with the mouse.

The default sorting is by NAME, but you can change the sort order by the /O<D,E,S> switch.

/OD = sort by date

/OE = sort by extension

/OS = sort by size

Note that the directories are ALWAYS sorted by name. These switches only apply to normal files.

Other switches are;

/W = use wide list format (valid only in BIGWCL)

/S = list matching files in all subdirectories

(cannot be used in addition to any other switch, files are NOT sorted at all, and the output cannot be redirected to a file or the printer)

NOTE: The DIR command shows in its first column the attributes of each file in the directory, enclosed within "<>"

H stands for Hidden

S stands for System File

R stands for Read Only

A stands for Archive (i.e, normal file)

DIR stands for Directory (i.e, this is a sub-directory)

N/A stands for "No Attribute"

If a file has more than one attribute, they are all listed e.g. <HRSA> for the DOS system files.

Like with the DOS equivalent, the output of the 'DIR' command can be redirected to a FILE or to the printer (LPT1) with ">"

e.g. DIR \*.EXE > EXEDIR.TXT (output to a FILE)

DIR C:\WINDOWS > LPT1 (output to the PRINTER)

NOTE: If you use redirection, make sure there is a space both before and after the redirection sign ">" (as in the examples above). If you do not insert a space (e.g. "DIR \*.EXE>EXEDIR.TXT") you will probably only get an error message.

The DIR window show can be RESIZED and MOVED, and there is nothing to stop you from having many DIR windows open. It's quite a straight-forward matter to ensure that only one copy of DIR is running, but I am convinced that there are good reasons for allowing multiple copies. You can compare the contents of two directories by having DIR windows of both of them on screen, for example.

## **MD**

MD - Create a Directory (alternative command is MKDIR).

## **PWD**

PWD - Show the current directory.

## **CD**

CD - Change to a directory (alternative commands are CHDIR and CWD). Using this command you can also change to an ALIASed directory.



## **RD**

RD - Remove a directory. This will only work if the directory is empty of files (alternative command is RMDIR)

## GOTO

GOTO - Change to a directory for which an alias has been created in WCL.INI. You should create ALIASES under the "[Directories]" part of WCL.INI by using a text editor or by using the ALIAS command.

The GOTO command enables a user to change to long directory paths easily.

e.g. if the line "SYS=C:\WINDOWS\SYSTEM" exists in the "[Directories]" part of WCL.INI, typing the command "GOTO SYS" will cause WCL to change to C:\WINDOWS\SYSTEM.

## ALIAS

ALIAS - VIEW the current list of Directory Aliases in WCL.INI (the first 20), or CREATE a new Directory Alias, or CHANGE an existing one. If the command is used without any parameter, a list of current Aliases is presented.

To CREATE a new alias, or CHANGE an existing one, use ALIAS <ALIAS-NAME> <DIRECTORY-PATH>

e.g. ALIAS BACKUP C:\DOCUMENTS\SECRET\BACKUP

If you want to create an ALIAS for the directory in which you are, you can use a dot (".") for the directory path, e.g.,

ALIAS THIS-DIR .

## **HOME**

HOME - Change to the WCL directory (alternative commands are GOHOME and HOMEDIR).

## File Services

WCL supports a number of internal commands for file services. The supported internal commands operate similarly to the DOS equivalents. Sometimes however, there may be minor variations. The file commands are outlined below

COPY

DEL

DELTREE

COPYTREE

REN

TYPE

HIDE

REVEAL

SEEK

ADD

PRINT

ATTRIB

## COPY

COPY - Copy a file or a number of files. This again is similar to the DOS Copy command and wildcards are allowed. You can copy to another drive/directory, etc., or to the printer "LPT1" (alternative command is CP).

NOTE: You can create an ASCII file with "COPY CON <FILENAME>", just as under DOS (e.g., "COPY CON LOADWCL.BAT"). This is useful for quick creation of TEXT FILES from within Windows without loading the NOTEPAD, or any other Text Editor. When the "COPY CON command is invoked, an Edit Window is opened for the text to be typed in. Each line is NUMBERED by WCL, so you can know how many lines you have left (a MAXIMUM of 100 lines of text is permitted, and each line cannot be more than 128 characters in length).

NOTE that the editor is a LINE EDITOR, just as in the DOS command line. Each line must be terminated by a Carriage Return and you CANNOT go back to edit previous lines.

When the editing is complete, type a period or full stop (".") on a line by itself, or type "end" on a line by itself to finish. It is at this point that the file is written to Disk.

The Lines Numbers supplied at the edit screen by WCL will NOT be written into the file, neither will the "end" or the period "." which inform WCL that you have finished editing.

NOTE: That you can also copy a file to the printer. "LPT1" and "PRN" are the only printer ports supported.

e.g. "COPY COMMANDS.SUM LPT1"

This will cause the file COMMANDS.SUM to be printed.

The COPY function tries to ensure that there is enough space on the destination drive for the files to be copied, on a file-by-file basis. If there is insufficient space for a file, there will be an error message to that effect, but the function will then proceed to try and copy any other file listed for copying. This is better than DOS in that DOS terminates the COPY function when there is insufficient space for ANY file, even if there are smaller files that will fit into the target drive. WCL will copy these smaller ones.

The COPY function also tries to verify that the actual number of bytes copied are equal to the size of each Source file. If there is any discrepancy in the sizes of the copied file and it's copy, there is an error message informing you of this, and the copy is deleted.

## **DEL**

DEL - DELeTe a file or a number of files. This again is similar to the DOS equivalent (alternative command is RM).

# COPYTREE

**COPYTREE** - This command attempts to copy a file specification in a given directory tree. This includes all the files matching the required specifications in that directory, and in its subdirectories.

The command attempts to re-create the directory tree structure of the **SOURCE** directory on the **TARGET** drive/directory. If a particular sub-directory in the tree cannot be created for some reason, the files that belong there will be copied into the root target directory.

If there is any problem with copying any file, the process will abort.

This command has certain restrictions. If it is used on the **ROOT** directory of any drive, it will **NOT** re-create the directory tree structure on the target drive/directory. It will just copy all the matching files into the target directory - period.

The syntax for the command is

**COPYTREE <FILESPEC> <TARGET DIRECTORY>**

If no directory path is supplied for the "filespec" then it will assume that the directory tree to be copied is the current directory.

Examples;

1. **COPYTREE C:\WP\\*.DOC E:\MYDOCS**

Means copy all the .DOC files in C:\WP and ALL its sub-directories, to E:\MYDOCS, re-creating the directory structure of C:\WP under the directory E:\MYDOCS.

2. **COPYTREE \*.\* G:\BACKUP**

Means copy all the files in the current directory and ALL its sub-directories, to G:\BACKUP, re-creating the directory structure of the current directory under the directory G:\BACKUP.



## DELTREE

DELTREE - This command attempts to delete ALL the files in a given directory tree. This includes all the files in that directory, and in its subdirectories. It then attempts to erase all the subdirectories in that directory tree. An alternative command is NUKE.

### NOTE:

I have implemented this command against my better judgment, because users demanded it. I do not think that deleting files should be made easy, since recovering them again may be impossible. In my opinion, DELTREE is a command that is best left well alone. If anybody proceeds to use it, I am cannot accept any responsibility for any loss of data that may ensue.

Because of the drastic nature of what DELTREE does, I have imposed some limitations;

1. You will be asked to confirm TWICE that you wish to proceed.
2. You must supply the name of a valid directory to the command. Just typing "DELTREE" will be rejected. You need to type something like "DELTREE D:\JUNKMAIL"
3. The command will reject any attempt to apply it to the ROOT directory of any drive.

e.g., "DELTREE \"

or "DELTREE C:\\"

these will NOT be accepted.

4. If there is any problem at all with deleting any file, then the process will abort.

## **REN**

REN - RENAME a file. This can be used on only one file at a time (alternative command is MV).

## **TYPE**

(display the contents of an ASCII file, 20 lines at a time. Note that you should not put the "<" character before the file name (unlike DOS).

e.g   TYPE MYFILE.TXT

or     MORE HELLO.DOC (not "MORE<HELLO.DOC")

## **HIDE**

HIDE - Hide a file or a number of files by setting their attributes to "hidden" (alternative command is CONCEAL).

## **REVEAL**

REVEAL - Restore a file or a number of files from "hidden" to normal (alternative command is UNHIDE).

## SEEK

SEEK - Try to locate a file or a group of files which match the specified filespec. The whole drive is searched for the files, and any matches found are listed. This command accepts wildcard characters. An alternative command is LOCATE.

e.g. "LOCATE WINWORD.EXE" - will look for all occurrences of WINWORD.EXE.

"SEEK WP\*. \*" - will look for files matching this specification.

This command can now take an extra parameter ("/DELETE") after the file specification. This is useful for getting rid of files of a particular specification. The deletion takes place in the current directory tree only. If you want to use it to delete a file specification through out the whole drive, you have to run this from the ROOT directory.

Use this parameter with care! You are only given ONE warning.

Example;

SEEK \*.BAK /DELETE

This will seek for all files with a \*.BAK extension, in the CURRENT directory tree, and delete any matching ones.

If the file specification is " \*.\*", the /DELETE parameter will NOT be accepted.

## ADD

ADD - Add the contents of one file to another. The file that you want to ADD TO is to be specified LAST, and the file that you want to add to it is to be specified FIRST (alternative command is CONCAT).

The syntax is thus;

```
"ADD <File to Add> <File Added To>"
```

e.g. "ADD SECOND.TXT FIRST.TXT"

This will append or add the contents of SECOND.TXT to FIRST.TXT. This means that after the operation, the file FIRST.TXT will now contain both the original contents of FIRST.TXT, with the contents of SECOND.TXT.

If for Example, FIRST.TXT originally contained "ABC" and SECOND.TXT originally contained "DEF", after the ADD operation, FIRST.TXT will now contain "ABCDEF". The contents of SECOND.TXT remain unchanged.

Always remember that the SECOND file to be specified is the file that will be ADDED to and that what will be added to it are the contents of the FIRST file to be specified.

Note: You CANNOT use wildcards in this command.

## **PRINT**

PRINT - Print a file, i.e., send it to the printer "LPT1" (alternative command are LPR and LPT).



# ATTRIB

ATTRIB - VIEW and/or CHANGE the attributes of a file or a group of files. To VIEW the attributes of a file, use ATTRIB <FILENAME> You cannot use wildcards if the ATTRIB command is used in this way.

To CHANGE the attributes of a file or files, use ATTRIB <ATTRIBUTES> <FILESPECS> You can use wildcards when the ATTRIB command is used in this way.

The ATTRIBUTES are represented by

R for READ ONLY;

S for SYSTEM FILE;

H for HIDDEN;

A for ARCHIVE.

You turn them ON or OFF by supplying a plus (+) or minus (-) AFTER the attributes.

e.g ATTRIB +RH HIDDEN.DOC (set HIDDEN.DOC to Read Only and Hidden)

e.g. ATTRIB -RS +HA SYSTEM.DOC (set SYSTEM.DOC to Hidden and Archive, and remove the Read Only and System settings)

## Miscellaneous Services

WCL offers a number of services which do not readily fall under any of the previous headings. Thus they are all grouped under the miscellaneous services heading. The miscellaneous commands are outlined below

SAY  
HELP  
SUM  
FREE  
BEEP  
PLAY  
DOS  
TYPEWRITE

## **SAY**

SAY - Show a Dialog Box displaying whatever is typed after this command.

## **PLAY**

PLAY - Play back any .WAV sound file. For example, to play the sound file CHIMES.WAV in the windows directory, type "PLAY CHIMES.WAV". Note that Windows requires a sound card to be installed before sound files can be played. If no sound card is installed, this command will produce no result. Alternative command is SOUND.

## **ABOUT**

ABOUT - Show information about WCL (alternative commands are VER and ID).

## **HELP**

HELP- Load this help screen (alternative commands are H and ?).

## SUM

SUM - Load the Windows Notepad program with WCL.SUM. NOTE that WCL.SUM is a plain ASCII text file. (alternative commands are H2, HELP2, and ??).

## **FREE**

FREE - Show the amount of free space on the drive which you specify after this command (e.g. FREE C: or FREE A:).



# **BEEP**

BEEP - Make the annoying beep sound.

## **DOS**

DOS - Open a DOS Shell. You return to Windows by typing "exit" (alternative command is SHELL).

## TYPEWRITE

TYPEWRITE - This takes WCL into "Type Writer Mode". You are presented with an Edit Window wherein you can type text. When you press <ENTER> the LINE of text is sent to the printer ("PRN"). This command thus turns your Windows and Printer into a pretend Electric Typewriter. You can type as many lines of text as you wish, but bear these in mind;

[a] Each line must terminate with a carriage return

[b] Each line must not be more than 78 characters long

[c] You can have empty lines, just by pressing <ENTER>

[d] This command will NOT work properly with Page Printers (i.e., Laser printers). This is because lasers print one page at a time, and not line by line like dot matrix, inkjet, and daisy wheel printers.

To EXIT from typewriter mode, just type "END" on a line by itself, or a full stop "." ("period" in American) on a line by itself.

# System Services

WCL offers a number of system services. Some of the commands are named like some internal DOS commands, but there are several which are unique to WCL. The system commands are outlined below.

In addition to the system services listed below, WCL allows you to use an "AUTOEXEC" batch file. This file is read everytime Windows is loaded, but only if WCL is your Windows Shell. This file should be called AUTOEXEC.CBF and should reside in your WCL directory, or in any directory which is in the DOS path. This file is treated as any normal WCL batch (.CBF) file, and should contain only commands that you wish to run EVERYTIME Windows is loaded. Note that batch commands may behave strangely because of the re-entrant nature of Windows and Win-OS2.

Please NEVER use WCL batch files in situations where things depend on commands being executed in a certain order. There is no way of telling the order in which the commands in your WCL batch file will be executed by Windows. Please note this warning.

BACKUPTHEINIS

CHANGE

CHG2

CLS

COMMAND\_ALIASES

DATE

DO

DOSKEY

EXIT

GETCOLOR

HALT

KEY\_ASSIGNMENTS

KILLPROG

LISTCOMMANDS

LISTWINS

NEWCOMMAND

PATH

PROMPT

RENAMEWIN

RESTART

SAVE

SET

SETCOLOR

SETDATE

SETTIME

SPAWN

SYSDIR

TIME

UPDATE

WINDIR

WINLOAD

WINRUN

WINSHELL

## **BACKUPTHEINIS**

BACKUPTHEINIS - Make backup copies of the WIN.INI and SYSTEM.INI files. WIN.INI is backed up as WIN.WCL and WIN2.WCL, and SYSTEM.INI is backed up as SYSTEM.WCL and SYSTEM2.WCL. Alternative command is BACKINI.

## **CHANGE**

CHANGE - Load the WIN.INI, SYSTEM.INI, and WCL.INI files into the Windows Notepad program for editing (alternative commands are CHG and CONFIGURE).

## **CHG2**

CHG2 - Load WCL.INI into the Windows Notepad program for editing (alternative command is WCLINI.).

## COLOR

COLOR - Change the color settings for text-color, text-background, and wallpaper, in WCL.INI. The command takes 3 parameters which determine each of the color settings. The settings that you specify are written to WCL.INI and will take effect when next you run WCL. The available colors are discussed in relation to the INI file settings, above. Alternative command is SETCOLOR.

e.g.,     COLOR black white white



## **GETCOLOR**

GETCOLOR - Show the current color settings for TEXT-COLOR, TEXT-BACKGROUND and WALLPAPER, in WCL.INI. Alternative command is GETCOLORS.

## **CLS**

CLS - Clear the screen. In WCL, this does nothing. In BIGWCL, it clears the screen, INCLUDING the contents of any scroll-back buffer.

## **WINSHELL**

WINSHELL - Change the "SHELL=" setting in SYSTEM.INI. The command takes one parameter (i.e., the new Windows Shell). If no parameter is supplied, the name of the current Windows Shell is presented.

e.g. WINSHELL WCL.EXE

This changes the Windows Shell to WCL.EXE

## **WINRUN**

WINRUN - Change the "RUN=" setting in WIN.INI. The command can take more than one parameter, each of them separated by spaces. The supplied parameters will replace the ones currently on the "RUN=" line. If all you want to do is to ADD extra programs to the "RUN=" line (as opposed to REPLACING the current one) then put a "+" sign BEFORE the first parameter

e.g., "WINRUN + DRWATSON.EXE WRITE.EXE"

this will ADD the two named programs to any one that is currently there.

(If no parameter is supplied, the current setting is presented).

To delete all the settings on the line, type "WINRUN NIL".

## **WINLOAD**

WINLOAD - Change the "LOAD=" setting in WIN.INI. The command can take more than one parameter, and operates exactly like the WINRUN command.

## **EXIT**

EXIT - Quit from WCL. If WCL is your Windows Shell, then this will quit from Windows. You will be invited to confirm that you do want to quit (alternative commands are QUIT or pressing ESC)

## **HALT**

HALT - Same effect as with "EXIT" ,except that this command will exit Windows, whether or not WCL is your Windows Shell (alternative command is CLOSE).

## **SAVE**

SAVE - Save the current state of the Windows desktop (the desktop is saved into a file called WCL.DSK in the Windows directory. This command also and saves the current WCL window co-ordinates and system settings (e.g., the current WCL prompt, the current Windows Shell, etc.) into the WCL.INI file. IF WCL is your Windows Shell, the saved Windows desktop will be restored when next you run WCL.



## **UPDATE**

UPDATE - Update the WCL system settings by reading the WCL.INI file again. It is to be used only when you have changed the contents of the WCL.INI file in the current session and you want the changes to take effect immediately without EXITing and restarting WCL.

# **PATH**

PATH - Display the current DOS path settings

## TIME

TIME - Display the current time and date.

## **DATE**

DATE - Display the current time and date.

## **SETTIME**

SETTIME - Set the system time. Format is hh:mm:ss.  
e.g. SETTIME 16:30:45

## **SETDATE**

SETDATE - Set the system date. Format is dd:mm:yyyy.  
e.g. SETDATE 22:04:1993

## **SET**

SET - Show selected DOS and Windows environment settings. Note that this only **SHOWS** you the settings. You cannot use the SET command to change any of the environment variables.

## PROMPT

PROMPT - Show the current WCL prompt, or change it to whatever is typed after this command.

e.g. PROMPT %

This gives you the UNIX percentage prompt

If you want a space to appear after your prompt, add a hash (" #") to the end of the prompt. e.g. "PROMPT FRED>#" ---- this will change the prompt to "FRED> ") To return the prompt to one that shows the current directory, type "PROMPT \$P\$G". Any prompt that is not \$P\$G is taken literally. No other "\$" setting is supported. Please note this fact. Note also that you should NOT use the hash for "\$P\$G"



## **RESTART**

RESTART - Shut down Windows and restart Windows again (valid only for Windows 3.1; alternative command is WIN).

## COMMAND ALIASES

COMMAND ALIASES - Users can create an alias for any command, up to a MAXIMUM of 30 aliases. This has required a new "[commands]" section to be added to WCL.INI, just before the "[directories]" section. Unlike the directory aliases which require WCL.INI to be read each time, command aliases are loaded into memory only ONCE - when WCL is loaded. Thereafter, they are processed from memory, until you exit the current WCL session. This makes the feature as fast as internal WCL commands. But it also means that any new command alias that is created in the current WCL session will not be evaluated until the next time you run WCL (unless in cases where the new command alias was created by using the "NEWCOMMAND" command).

Restrictions are that the whole line on which the alias exists cannot be more than 79 characters in length, and that you have to create the command aliases by manually adding each new alias to the "[commands]" section in WCL.INI, or by using the new command "NEWCOMMAND" (see below).

Examples of manual entries in WCL.INI;

```
SYSDIR=DIR C:\WINDOWS\SYSTEM  
CWCL=CD C:\WCL  
CT=COPYTREE
```

Note that the command aliases are evaluated *\*before\** internal and external commands. Thus, if you create an alias with the same name as a WCL internal command, it is that alias, instead of the WCL internal command that will be executed.

Note also that WCL interprets the aliased commands LITERALLY. Thus, it is the user's responsibility to ensure that the commands for which aliases are being created are correct and non-destructive.

Finally, do NOT create a command alias which involves the execution of a WCL batch file. Please note this point, as I cannot guarantee how the whole thing will be evaluated, if it involves the execution of a .CBF batch file.

## NEWCOMMAND

NEWCOMMAND - This command is for the purpose of creating a new command alias (see above), without having to edit WCL.INI manually. This command inserts the new alias into WCL.INI, and retains it in memory for use during the current session. Note that if this command is used to replace a command alias which already exists in WCL.INI, the new one will not take effect until when you next run WCL. Use it only to create NEW command aliases.

### Syntax

NEWCOMMAND <Alias Name> <Command>

### Examples;

```
NEWCOMMAND BACKIT COPY *.DOC A:\
NEWCOMMAND CT COPYTREE
```

To delete a particular entry from WCL.INI, supply "NIL" as the command. Note that when you do this, the command alias WILL be deleted from WCL.INI, but it will still be active in memory, until when next you run WCL. So if you type LISTCOMMANDS to see the currently active command aliases, the one that has just been deleted will still be there. Please note this point.

## **LISTCOMMANDS**

LISTCOMMANDS - produces a list of the first 20 command aliases.

# **SYSDIR**

SYSDIR - Changes to the Windows SYSTEM directory.

## **WINDIR**

SYSDIR - Changes to the Windows directory.

## **DOSKEY**

DOSKEY - Use this command to enable or disable DOSKEY emulation during the current WCL session. Nothing is written to WCL.INI. This command takes one parameter (either "ON" or "OFF"). Note that using this command also affects support for assigning commands to the function keys. If the command is typed with no parameter, then you are just shown the current status of the DOSKEY emulation.

## **LISTWINS**

LISTWINS - displays a list of all the currently active processes, with their process ID numbers. You need this information in order to use the RENAMEWIN or KILLPROG command. An alternative command is LW.



## KILLPROG

KILLPROG - you can use this command to terminate any currently active process, by its process ID number. Get a list of all the currently active processes, with their process ID numbers by typing "LISTWINS". You then supply the process ID number of the program you wish to terminate, to KILLPROG. An alternative command is KP.

Note that once you supply an ID number to KILLPROG, the program which is represented by that ID number is terminated WITHOUT WARNING. Also, note that LISTWINS does not list some programs because I consider that it will be foolish to terminate them. Thus, if you type KILLPROG and then supply an arbitrary number, it may actually represent the ID of a running process, and that process WILL be terminated.

Therefore, use this command with care, and use it only with process ID numbers supplied by LISTWINS. I cannot accept any responsibility for wrongful use of this command (or, indeed, any other WCL command).

Example: KILLPROG 4309

This will terminate the program which has the ID number 4309, without warning.

## RENAMEWIN

RENAMEWIN- you can use this command to rename the main window of any active process, by its process ID number. Get a list of all the currently active processes, with their process ID numbers by typing "LISTWINS". You then supply the process ID number of the program you wish to rename, to RENAMEWIN, and you also supply the new name that you wish to give to that window. The new name is active until you close down the program, or rename it again.

This command does NOT have a permanent effect, and so is quite safe. Alternative commands are RENW, and RENWIN.

Example: RENAMEWIN 4309 My Greatest Windows Hack

This will rename the main window of the program which has the ID number 4309, to "My Greatest Windows Hack", until you exit the program, or until you rename it again.

## DO

DO - with regard to the way WCL runs external programs, some users have complained about the fact that WCL sometimes changes to the directory in which the executable for the program was found, before running it. This feature exists for many reasons (partly to do with Windows itself), but it can be circumvented. I have decided to keep that feature as the default, but to permit users to circumvent it. This is implemented when the user types "DO" before the name of the program to be executed.

If this is typed before the name of an external program then WCL will remain in the current directory while running that program, and will not change to the program's directory as it sometimes does. The only use of this command is as a prefix to whatever you would normally have typed. Thus if you would normally type;

**PKUNZIP WINCMD\*.ZIP**

you would now type;

**DO PKUNZIP WINCMD\*.ZIP**

Most people will never need to use this "DO" command, but it is there anyway.

# KEY ASSIGNMENTS

## FUNCTION KEYS (F1=F9, and F11-F12)

## CONTROL KEYS (CTRL-A to CTRL-Y)

WCL supports the assigning commands to FUNCTION KEYS (F1 to F9, and F11 to F12), and the CONTROL KEY + AN ALPHABET (CTRL-A to CTRL-Y, but MINUS CTRL-C, CTRL-G, CTRL-H, CTRL-M, CTRL-T, and CTRL-X - these are reserved). Note that this feature is disabled if DOSKEY EMULATION is turned off.

The commands have to be assigned manually in KEYS.WCL, which is a plain ASCII file that can be edited with Notepad. Any command can be assigned to any of these keys, and any entry is executed IMMEDIATELY, EXACTLY as it appears in KEYS.WCL.

### Examples:

F1=HELP

F2=

F3=\*

F4=

CTRL-A=WPWIN STATUS.WP

CTRL-B=

CTRL-D=

..... and so on .....

This is how you assign commands to the function keys and the control keys. I have pre-set F1 for HELP, and F3 to bring up the last command (the asterisk means "fetch the last command"). You can change these settings, and you can assign any command to any of the others (except F10). The commands are executed IMMEDIATELY after the key is pressed (ie you do not need to press ENTER). None of the control keys is preset.

Example: F2=COPY \*.DOC A:\

With this setting, when you press the F2 key, all the files with a .DOC extension are copied to drive A:

A known problem with this feature is that sometimes you may have to press a function key twice, before the command is executed. I have so far been unable to find a way of remedying this situation. The problem does not exist with the control keys.

## SPAWN

With regard to the way WCL runs DOS programs, some users have complained about the fact that WCL sometimes closes the DOS window before they can read the output from the window. This is actually a function of Windows, not WCL. However, I have provided an effective (if inelegant) way to bypass this.

This is implemented by prefixing the program with the "SPAWN" command. When the user types "SPAWN" before the name of a DOS program to be executed, WCL puts everything that appears after "SPAWN" into a batch file, and executes the file. When the file has finished executing, you are invited to press ENTER to return to WCL.

Example: SPAWN PKUNZIP -V \*.ZIP | MORE

This will run PKUNZIP with a pipe into the MORE command. When PKUNZIP finishes the DOS window will still be open, and then you will be invited to press ENTER to return to WCL.

### NOTE:

With this command, you can also get WCL to execute the COMMAND.COM version of internal DOS commands (eg DIR, PATH, SET, COPY) - instead of the WCL version.

e.g.

"DIR \*.DOC" - this will execute WCL's own DIR command

but;

"SPAWN DIR \*.DOC" - this will execute the COMMAND.COM version of DIR, in a separate DOS window.

NOTE: do NOT use this command to run Windows programs. It will most certainly NOT work.

# Introduction

**WCL contains too many features and commands to be fully summarised here. Please read this help file carefully.**

Windows Command Line (WCL) is a command line interface program for Windows 3.x and Win-OS/2. The program simulates the infamous C:\> prompt of the DOS command line, but from within Windows, or while running as a "seamless" Windows application on the OS/2 Workplace Shell desktop. This is useful for those DOS hackers who find themselves having to use Windows for certain applications, or for people who want a very quick and easy way to multi-task Windows programs, either within Windows itself, or from the OS/2 desktop, or for those who like to have a command line window available at all times. From WCL, you can run all Windows, DOS and OS/2 (under OS/2 2.1) programs just by typing the program name, and pressing <ENTER> as you do would at the DOS prompt for DOS programs. When you run a program through WCL, the program's window becomes the Active Window. You can go back to WCL by clicking on any part of the WCL window that is visible to you, and then run other programs from there.

WCL consists of 3 main executables (1) WCL.EXE - the main executable (2) WCLDLL.EXE - library executable for WCL.EXE, and (3) BIGWCL.EXE - the "big" version of WCL.EXE, in the sense that [a] it's main window is big, and all the output is directed to that window, and [b] it is self-contained - unlike WCL.EXE, it does not require the library file WCLDLL.EXE.

WCL.EXE and BIGWCL.EXE are alternative forms of the main WCL program. There is nothing stopping you from using both of them, but the idea is that while some people will prefer WCL.EXE's small and unobtrusive main window, others may not like the fact that it uses popup windows for some of its output. The ONLY significant differences between WCL.EXE and BIGWCL.EXE lies in the size of their main windows, and the fact that all the output from BIGWCL.EXE is in the same main window.

## OS/2 version 2.1:

WCL has been tested extensively under OS/2 version 2.1, and has been designed to detect that operating system and adjust itself thereto. It works beautifully under OS/2. If WCL is run from within OS/2 version 2.1, either as a "seamless" application (i.e., from the Workplace Shell desktop), or in a full screen Win-OS/2 session, you can run DOS, Windows and OS/2 programs from the WCL prompt.

OS/2 users should please NOTE that WCL will only run DOS and OS/2 programs under OS/2 in the same way that the Program Manager will run them, since WCL uses the same API calls. Some OS/2 programs will not run at all, if run from a Win-OS/2 session, and some DOS programs behave quite strangely if run from Win-OS/2.

### **PATH:**

If the application you wish to run is not in a directory which is in DOS Path, you will have to supply the full path name (e.g. "C:\WPWIN\WPWIN", to run WordPerfect for Windows, if C:\WPWIN is not in the DOS Path). If the application is situated in a directory that is in the DOS Path, all you need do is type its name, and press <ENTER> (e.g. "WRITE" <ENTER>, to run Windows Write).

All Windows programs can be run from within WCL. This includes DOS programs for which a Windows .PIF file exists. Most DOS programs can also be run directly from WCL without creating a PIF file for them. In this case, they will run in full screen mode.

Note that most internal DOS commands (i.e, those that are resident in COMMAND.COM) can NOT be run directly from WCL. However, a number of DOS-like commands are supported through built-in technology. Below is a list of them;

[1] CD or CHDIR (change directory)

[2] MD or MKDIR (create a new directory)

- [3] RD or RMDIR (remove/delete a directory)
- [4] DEL or ERASE (delete files. Wild cards are accepted)
- [5] REN or RENAME (rename one file; Note - You CANNOT use wildcards!)
- [6] COPY (copy files. Wild cards are accepted.)
- [7] TIME (show current system time)
- [8] DATE (show current system date)
- [9] SET (show SOME environment variables)
- [10] PROMPT (Change the WCL prompt)
- [11] TYPE or MORE (display the contents of an ASCII file)
- [12] PRINT (print a file)
- [13] DIR (list the files in the directory)

Apart from changing drives (e.g. "A:" to change to drive A or "D:" to change to drive D, etc.,) INTERNAL DOS commands different from those listed above cannot be directly run from WCL. Attempting to run them will either produce an error message from Windows, or lead to the DOS prompt being invoked through a DOS Shell.

External DOS commands (i.e. those which have their own .EXE, .COM, or .BAT files, e.g. "FORMAT", "GW BASIC", "XCOPY", etc.) can normally be run directly from WCL. However, I would not attempt to run programs such as "CHKDSK" or programs which access the hardware directly (such as disk compressors) when in Windows. A lot of grief can result from this. Basically, any DOS program which can be used safely under Windows can be used safely in WCL since everything that WCL does is done through Windows API calls (i.e. Windows itself does all the actual processing. WCL only acts as a command line interface between you and Windows).

### **NOTE: the command "DO"**

With regard to the way WCL runs external programs, some users have complained about the fact that WCL sometimes changes to the directory in which the executable for the program was found, before running it. This feature exists for many reasons (partly to do with Windows itself), but it can be circumvented. I have decided to keep that feature as the default, but to permit users to circumvent it. This is implemented when the user types "DO" before the name of the program to be executed.

If this is typed before the name of an external program then WCL will remain in the current directory while running that program, and will not change to the program's directory as it sometimes does. The only use of this command is as a prefix to whatever you would normally have typed. Thus if you would normally type;

**PKUNZIP WINCMD\*.ZIP**

you would now type;

**DO PKUNZIP WINCMD\*.ZIP**

Most people will never need to use this "DO" command, but it is there anyway.

You can dispense with having to type "DO" all the time by setting the "DO=" line in WCL.INI to "1", or "ON" (i.e., "DO=1"). With this setting, WCL will behave as if you have typed "DO" before the name of \*every\* program that you want to execute. This setting is NEW (with version 7.0), and is disabled by default.

If there is any program which you should not run under Windows, then please do NOT attempt to run it via WCL.

Note that you can use the UNIX names of some of these commands, although they do not operate like the UNIX commands.

e.g.

CP for COPY

MV for RENAME

RM for DELETE

CWD for CHANGE DIRECTORY

LS for DIRectory listing

These commands operate more or less like their DOS equivalents, except that you cannot use wild cards in the RENAME function. For file copying, wildcards are accepted for SOURCE file specifications only. You cannot use wildcards in TARGET file specifications.

e.g

COPY \*.DOC A:\MSDOS - This is valid

COPY \*.DOC A:\MSDOS\\*.BAK - This is invalid.

REN \*.DOC \*.TXT - This is invalid

Both the COPY and DIR commands produce their own Windows on the screen. However, if you are running BIGWCL.EXE, all the output is in the main window. BIGWCL.EXE is almost an exact reproduction of the MSDOS prompt, within Windows/Win-OS/2.



## Command\_Line\_History

WCL supports a limited form of command line history by keeping a record of the LAST 30 commands typed at the prompt. There are a number of commands for accessing the history function. They are enumerated below;

1. **!!** - (two exclamation marks) - this will execute the most recent command.
2. **!** - (one exclamation mark) - If this is typed by itself, WCL will list the last 20 commands (each of them with a number) in a message box. When the message box is closed you are prompted for the number of the line that you want to execute. The command is then executed.

If you do not want to execute any of the listed commands, type 0 (zero) or just press <ENTER>. If the single exclamation mark is followed by a space and then a number (e.g., **! 10**), WCL fetches the command with that number (if any exists). Thus for example, **! 6** means fetch the sixth to the last command. You can use a hyphen instead of a space (e.g., **!-6**)

3. **LIST** - Show a numbered listing of the last 20 commands typed at the WCL prompt (alternative command is **HISTORY**).
4. **CLEAR** - Clear the command line history list. This gets rid of all the entries present on the list of the last 20 commands. The list will then start to build from the scratch. It is a great way to stop prying eyes (e.g., the boss) from seeing what commands you have been typing all day.

### DOSKEY EMULATION

WCL features support for a LIMITED emulation of the DOSKEY function of scrolling through a list of past commands (by using the arrow keys - LEFT or UP arrow keys, or CTRL-Z for ("up") and DOWN or RIGHT arrow keys, or CTRL-X (for "down")).

This feature is enabled by a setting "EMULATE-DOSKEY" in WCL.INI. A setting of "1" or "ON" enables this feature, and any other setting disables it (eg "EMULATE-DOSKEY=ON"). It can also be enabled or disabled temporarily within WCL by typing "DOSKEY ON" or "DOSKEY OFF".

One limitation is that you can only edit the commands by using the BACKSPACE key.

A known problem with this feature is that sometimes you may have to press an arrow key twice, before you get the scroll. This does not happen when you use CTRL-Z or CTRL-X. I have so far been unable to find a way of remedying this situation. If this bothers you, then you should use CTRL-Z to scroll up, and CTRL-X to scroll down.

## Batch\_Files

WCL supports sequential processing of commands by allowing you to put commands into a BATCH FILE. This batch file must have ".CBF" as its extension. "CBF" stands for "Command Batch File".

e.g "COPYBAK.CBF"

Batch files can contain any command that WCL supports - ie. internal WCL commands, DOS .BAT, .EXE and .COM programs, and Windows programs. The file batch file must be in ASCII format, and each command must be on a separate line. Each batch file can be up to 20 lines in length. However, it cannot contain another .CBF file.

Once set up, all you need to do is to type the name of the batch file at the WCL prompt. You do not need to type it's extension. With the example above, you only need to type "COPYBAK". WCL will then try to execute the commands in the file on a line-by-line basis. This may result in some interesting screen manoeuvres as each program is given the input focus by Windows, and tries to display its messages and main window.

Remember that Windows programs do not have the whole PC to themselves, unlike DOS programs, so each Windows program will allow another to be immediately loaded after it, as soon as it sets up its main window. If the batch file contains a mixture of DOS and Windows programs, the screen manoeuvres are yet more interesting. The import of this is that the processing of batch commands in Windows will not always be as you expect, if looked at from a DOS batch file point of view. This is due to the nature of Windows itself, and there isn't much that I can do about it.

### **WARNING:**

Please NEVER use WCL batch files in situations where things depend on commands being executed in a certain order. There is no way of telling the order in which the commands in your WCL batch file will be executed. Please note this warning.

You can pass parameters to your WCL batch files, just as in DOS. To do this, use "%1" as you would in DOS. This feature is still quite new, but it has worked well so far in my tests. You will have to experiment to see what works in this regard. Please use this only for the purpose of passing parameters to external programs. Do not use it for WCL's internal commands. Note: WCL can only process a maximum of 3 parameters in this way (i.e., %1, %2, and %3).

### **NOTE:**

Please ensure that batch files do NOT have the same names as any DOS or Windows program file that you will call from the batch files. For example, if you will call KERMIT.EXE from you batch file, make sure that the batch file is not called KERMIT.CBF - if you do not heed this advice, you are SURE to get a SYSTEM CRASH when you try to run the batch file. Please note this warning.

### **AUTOEXEC.CBF**

WCL supports an "AUTOEXEC" batch file for Windows/Win-OS/2. If WCL is your Windows Shell, you can put any commands that you wish to be executed every time Windows is started in a WCL batch file called AUTOEXEC.CBF. WCL will then run the commands in this file whenever Windows is started. If WCL is not your Windows Shell, the AUTOEXEC.CBF file will be ignored.

Example of a .CBF file's contents;

```
SAY This is a test .CBF file!  
CD C:\WINDOWS
```

```
COPY *.INI A:\  
CD C:\DOCS\LETTERS  
COPY *.LET A:\LETTERS
```

```
SAY I have finished the back ups
```

This file starts by printing a message that it is a test .CBF file. It then backs up all the .INI files in the Windows directory, and all the .LET files in the C:\DOS\LETTERS directory. It finishes by telling you that its has completed the back ups. "SAY" messages may actually appear BEFORE the operations which they claim to have completed. This again is due to the nature of Windows.

## INI\_File\_Settings

There are various entries in the file WC.INI which determine the way in which WCL works. Below is an explanation of the purpose of each of the settings, including the defaults;

### **DO=0**

With regard to the way WCL runs external programs, some users have complained about the fact that WCL sometimes changes to the directory in which the executable for the program was found, before running it. You can circumvent this feature now. This is implemented when the user types "DO" before the name of the program to be executed. This is explained in more detail under the "DO" command.

You can now avoid having to type "DO" all the time by setting the "DO=" line in WCL.INI to "1", or "ON" (i.e., "DO=1"). With this setting, WCL will behave as if you have typed "DO" before the name of \*every\* program that you want to execute. This setting is NEW (with version 7.0), and is disabled by default.

Note that turning on this setting may cause some programs not to work properly by virtue of not being able to locate their own data files. Thus it may be better to leave this setting disabled, and to use the "DO" command on a case-by-case basis.

### **WINDOWLENGTH=50**

(This is the length of the WCL window. You can reduce or increase the number from 50. Note that to have enough space for typing commands, 42 is the suggested minimum).

### **LOCATION-HORIZONTAL=1**

(this is the location of the LEFT HAND side of the WCL window. By default, this is the left edge of the screen. You can increase this if you want the window to be moved to the centre, or the right side of the screen for example.

NOTE: assuming that the screen width is 80 characters, for a Standard VGA screen, multiply each character by 8. So, for the left side of the window to be moved to the CENTRE of the screen for example, you can put LOCATION-HORIZONTAL=320).

The EFFECT of this setting depends entirely on the RESOLUTION of your screen. So for SuperVga modes (e.g.800x600; 1024x768) you will need to increase the multiplication ratio.

The easiest way of setting this is to move the WCL window to the desired location, leave it there, and then type "SAVE" at the WCL command prompt. This will cause the location of the WCL window to be saved in WCL.INI.

Note that when you change this setting, you have to allow for the length of the WCL window as set in WINDOWLENGTH (above).

### **LOCATION-VERTICAL=1**

(this is the location of the TOP of the WCL window. By default, this is set to the top of the screen. You can increase it if you wish to move the window DOWN, perhaps to the bottom of the screen.

NOTE: assuming that the screen length is 25 lines, for a standard VGA screen, multiply each line by 19. So, to move the window to the bottom of the screen, you can put LOCATION-VERTICAL=475).

This setting determines the TOP of the WCL window. The window itself occupies about 6 lines. So, you effectively have only 19 lines to play with. In the example given above, 475 is the 25th line of the screen. If you use that setting, you WILL NOT SEE any part of the WCL window (it the rest of it will be below

the bottom of the screen). The safe setting for the bottom of the screen on Vga mode (640x480) is LOCATION-VERTICAL=361

For SuperVga modes, you again have to increase the multiplication ratio.)

### **WCL-PROMPT=\$P\$G**

(This is the default mode of the WCL command line prompt. It displays the current Drive and Directory (like DOS). If this line is empty, then this is still the default prompt. If you wish to customise the WCL environment, you can change this setting. Anything after the "=" sign is taken LITERALLY and will appear EXACTLY as written. The only exception is "\$P\$G" which simulates the ubiquitous DOS prompt.

So you can simulate the famous DBase "dot prompt" by putting on this line, "WCL-PROMPT=."

You can also simulate the UNIX % prompt by "WCL-PROMPT=%" Alternatively, use your own name, "WCL-PROMPT=JOE BLOGGS>" (Note: The longer the prompt, the LESS space you have at the command line for typing commands)

If you want a space to appear after your prompt, add a hash (" #") to the end of the prompt. e.g. "PROMPT FRED>#" -- this will change the prompt to "FRED> ") To return the prompt to one that shows the current directory, type "PROMPT \$P\$G". Any prompt that is not \$P\$G is taken literally. No other "\$" setting is supported. Please note this fact. Note also that you should NOT use the hash for "\$P\$G".

You can change the prompt at the command line at any time by using the "PROMPT" command.

e.g. "PROMPT %" or "PROMPT .#"

This change will be saved into WCL.INI if you quit WCL through one of its own exit commands (e.g., "EXIT", "HALT", "QUIT")

### **EMULATE-DOSKEY=1**

This setting turns on support for a LIMITED emulation of the DOSKEY function of scrolling through a list of past commands (by using the arrow keys - LEFT or UP arrow keys, or CTRL-Z for ("up") and DOWN or RIGHT arrow keys, or CTRL-X (for "down")).

This setting also turns on support for assigning commands to FUNCTION KEYS (F1-F9, and F11-F12); and the CONTROL KEY + AN ALPHABET (CTRL-A to CTRL-Y, but MINUS CTRL-C, CTRL-G, CTRL-H, CTRL-M, CTRL-T, and CTRL-X - these are reserved). F10 also is reserved for use by Windows. You can put assign any command to any of the free keys by just putting the command after the "=" sign. WCL will execute the command EXACTLY as it appears here.

These key assignments are carried out manually in KEYS.WCL, which is just a plain ASCII file that can be edited with the Notepad or any other text editor.

A setting of "1" or "ON" turns this setting ON. Any other setting turns it OFF You can also turn it on/off in WCL by typing "DOSKEY ON" or "DOSKEY OFF"

A known problem with this feature is that sometimes you may have to press an arrow key twice, before you get the scroll. This does not happen when you use CTRL-Z or CTRL-X. I have so far been unable to find a way of remedying this situation.

One limitation is that you can only edit the commands by using the BACKSPACE key.

A known problem with this feature is that sometimes you may have to press an arrow key twice, before you get the scroll. This does not happen when you use CTRL-Z or CTRL-X. I have so far been unable to find a way of remedying this situation.

### **TEXT-COLOR=**

This setting determines the color of the text in the WCL windows. You can use any color here.

### **TEXT-BACKGROUND=**

This setting determines the color of the background of the WCL windows. Although you can theoretically use ANY color here, practically, you have to use the same color as you use for your "wallpaper" setting (below).

**Notes: for TEXT-COLOR and TEXT-BACKGROUND**

These settings should contain whole numbers (i.e., without decimals, or commas) that represent the colors that you want for the text and the window background respectively. Since users may be using any number of display cards and any number of screen drivers at any time, the color codes will vary significantly between systems.

If you ever want to return to the default BLACK text on WHITE background, leave these settings empty, and WCL will use the defaults. Also, because of difficulties that users may face with the use of numbers, I have decided to support a number of non-numerical color codes which are constant on systems with 16 or more colors. The colors that you may specify by NAME for the text color and the text background are;

cyan  
white  
black  
red  
green  
blue  
yellow  
magenta  
gray  
darkyellow

These can be entered in uppercase or lowercase letters - it does not matter.

If you want to use any color other than the above, then you have to use a numeric value that represents its color. Sorry, I can't help you further here. But if it helps, you can use hexadecimal values (ones that begin with \$00, and then are followed by SIX values). C or Pascal programmers will be familiar with these. The six values that follow the \$00 are RGB values, but used backwards (i.e., the first two for BLUE, the next two for GREEN, and the last two for RED). "FF" turns the value to full intensity, and "00" turns the color off. Any number between those two will vary the intensity.

e.g.,  
\$00000000 = black  
\$00FFFFFF = white  
\$00FF0000 = blue  
\$00808080 = gray  
\$000000FF = red  
\$0000FF00 = green

**WALLPAPER=**

This setting determines the color of the "brush" that Windows uses to paint the background of the main window. This can take one of 5 colors;

black  
gray  
white

gray  
lightgray  
darkgray

**NOTES:**

1. You should not use numeric values here.
2. You should use the same color here as you used for your text background, otherwise you will get very odd screens in all your WCL windows, and unsightly flashes in the BIGWCL main window.

**NOTE:**

The three above settings can be set either by manual editing of the WCL.INI file, or by using the new "COLOR" command, which writes the settings to WCL.INI for you. They then take effect when next you run WCL. If you want to see the colors which are already set in WCL.INI, type "GETCOLOR".

The syntax is COLOR <textcolor> <textbackground> <wallpaper>

e.g., "COLOR yellow black black"

**SAVE-DESKTOP=0**

(this setting *\*ONLY\** has effect when WCL.EXE is your Windows Shell. If set to 0, then the desktop is NOT saved when you exit from WCL. If set to 1 (one) then WCL will save the current state of the Windows Desktop (i.e., all active programs) when you exit. The next time you run Windows, WCL will automatically restore the Windows Desktop to the position it was when you last quit from WCL (i.e., all those active programs will be run automatically). The desktop is saved in a file called "WCL.DSK" in the Windows Directory. This file is in a binary format, so please NEVER try to EDIT it with a text editor. You can of course delete it any time you want.

NOTE: The Desktop will only be saved when you exit from WCL by using one of the WCL exit commands (i.e., "QUIT", "EXIT", "HALT", or pressing the ESCape key). If you exit by pressing Alt F4 or by selecting "Close" from the system menu, then the Desktop will NOT be saved. If you are fond of exiting Windows programs in these ways, then you can save the Desktop manually by typing "SAVE" at the WCL prompt, immediately before quitting.

**WINDOWLENGTH.BIG=75**

This is the setting for the length (or width) of the BIGWCL.EXE main window. In order for the DIR/W command to work properly, this setting should be at least 75 (note: that DIR/W is not supported in WCL.EXE).

**WINDOWHEIGHT.BIG=25**

This is the setting for the height of the BIGWCL.EXE main window. Any setting lower than 25 will be ignored. If you want a scroll back buffer in the BIGWCL main window, this setting can be increased - the higher the setting, the bigger the scroll back buffer (e.g., a setting of 250 will give a scroll back buffer of about 7 screens). This setting should NOT be higher than 300. Although you may get a bigger scroll back buffer with a setting of over 300, if the setting is too high, you may get general protection faults in Windows. 300 is a bit conservative as a maximum, but this gives a wide safety margin.

**LOCATION-HORIZONTAL.BIG=1**

This is the location of the TOP LEFT corner of the BIGWCL window.

## **LOCATION-VERTICAL.BIG=1**

This is the location of the TOP of the BIGWCL window.

## **BIGWCL-DEFAULT-FONT=0**

This is the setting for the default font used in the BIGWCL window. When the DEFAULT-FONT is set to ZERO (default) then the System Fixed Font is used. Other possible values are; 1 (this means use the ANSI fixed font); 2 (this means use the OEM fixed font); 3 (this means use the default font for screen device). Any other setting is ignored in favour of the default.

## **STARTUP1= ; STARTUP2= ; STARTUP3= ; STARTUP4=**

(These are for indicating the programs to be loaded by WCL every time you start a WCL session. They are looked at *\*ONLY\** if WCL is your Windows shell. If you retain Program Manager as your Windows shell, these lines are COMPLETELY IGNORED. WCL does not load the programs in your Windows start up group file, and this is the way of compensating.

So if for example, you want CONTROL.EXE to be loaded every time you start WCL, you can put "STARTUP1=CONTROL.EXE". If the programs are not in the DOS path, then you have to type in the FULL PATH of the program (e.g. "STARTUP2=D:\MYDIR\MYPROG\MYPROG.EXE"). NOTE that the program name/path must not exceed 78 characters, or it will be truncated.

Only 4 start up programs are supported here. If you must have more than 4, then put one on the line that reads "RUN=" and one on the line that reads "LOAD=" in your WIN.INI file. Alternatively you can create a WCL batch file (e.g., "STARTUP.CBF") and include its name in one of the startup lines. With such a batch file, you can load as many programs as you wish.

NOTE: The programs contained on the start up lines will be loaded EVERY TIME that a WCL session is commenced. So, if for any reason you are running multiple copies of WCL, EACH copy will load all the programs. So it is better to leave those lines as they are until you have finished configuring WCL for your system. If you are likely to want to run multiple copies of WCL, do not add anything to these lines).

## **CONFIRM-OVERWRITES=0**

This sets the behaviour of the File Copy routines. When set to 0 (zero; this is the default) existing files will be overwritten by the versions being copied, WITHOUT WARNING (this is like the DOS Copy command).

If set to 1 (one) then you will ALWAYS be prompted for confirmation before an existing file is overwritten.

NOTE: The WCL.INI file is polled for this setting only ONCE (when the program is loaded) so any change you make to this setting will take effect only after you run WCL again (or if you run another copy of it by typing "WCL" at the prompt, and Close the original copy)

## **BACK-UP-INI-FILES=1**

This setting is effective *\*only\** if WCL is your Windows Shell. If set to 1, then WCL will back up your WIN.INI and SYSTEM.INI files everytime Windows is started. WCL tries to make TWO backups of each file, with extensions of ".WCL". This is useful for restoring your Windows setup in cases when some program has messed up your INI files. If set to 0 (zero) then the backups will not take place.

## **IMPORTANT NOTES**



[1] There must be NO SPACES AT ALL between the entries on each line. e.g "WINDOWLENGTH = 50" is NOT valid because there are spaces both before and after the "="

[2] The responsibility for supplying correct and sensible values for these window co-ordinates is TOTALLY YOURS. The default settings are quite adequate for most needs, and you can always re-locate and re-size the window using your mouse.

[3] If WCL cannot find the file WCL.INI at startup time, then the default values explained above will always apply.

[4] The WCL.INI file is only read ONCE - when WCL is loaded. If you change any thing in the file, you will have to close and restart WCL for the changes to take effect. The only exception to this is with respect to directory aliases. When you use the "GOTO" command, WCL searches always WCL.INI for an alias for the name you supply.

[5] If you are experimenting with different settings for the WCL window, there is nothing to stop you from testing your settings on another copy of WCL. You can run another copy of WCL by typing "WCL" at the prompt. You will then see another copy loaded, and reflecting the window co-ordinates in the current version of WCL.INI. NOTE that if you have not changed the window coordinates, then the other copies of WCL will have their windows right on top of the current copies.

[6] If WCL is NOT your Windows shell, then the Start Up lines and SAVE-DESKTOP setting in WCL.INI will be ignored.

## **Disclaimer**

The WCL programs are supplied AS IS, without ANY WARRANTIES WHATSOEVER. I will accept NO RESPONSIBILITY for any loss or damage, financial or otherwise, consequent upon the use or purported use of WCL for any purpose whatsoever.

If these terms are NOT acceptable to you, then you have no licence to use or test WCL. You should DELETE the programs from your disks immediately.

## Registration

WCL is distributed under the Shareware principle. The program can be copied and distributed freely, as long as ALL the supplied files, including documentation (this file) are included, and NO ATTEMPT is made to modify any of the files. The program may not be supplied or bundled with any COMMERCIAL application without prior WRITTEN permission from me.

"Commercial" does NOT include Shareware, Freeware, or Public Domain programs. WCL may be bundled freely with Shareware, Freeware and Public Domain programs. All I require in these cases is a letter or Email message informing me of what program(s) you have bundled WCL with.

The Shareware principle means that you get a chance to EVALUATE the program free of charge for a reasonable period of time (usually 30 days). It does not mean that you will NOT have to pay for the program. If you find WCL useful and would like to continue using it then you are requested to please REGISTER your copy with the author.

### **REGISTRATION FEE:**

**£18.00** (U.K. STERLING)

**\$26.00** (U.S.)

**\$30.00** (Canadian): British Columbia residents should add 7% Sales Tax

**\$40.00** (Australian)

**Kr170.00** (Danish)

**Prices are subject to change without notice.**

If you are outside the U.K. and Ireland, please look in the section titled "REGISTRATION SITES" (below) for the details of registration sites which are close to you, and in which you can register in your own currency, or by credit card. This will save you having to send foreign cheques to me, thereby incurring bank charges.

Users from outside the United Kingdom who wish to send their registration fee to me in the U.K. should please send or an International Money Order drawn out in STERLING only. Otherwise, if sending cheques drawn out in currencies other than Sterling, please add £3 (Three Pounds Sterling) to cover U.K. bank charges. Thus, for example, if you are sending a cheque that is drawn on a bank in the U.S.A, you need add \$4.50 to the registration fee to cover U.K. bank charges (meaning \$US30.50 in all).

Please note that the extra £3 is COMPULSORY if you are sending me a cheque that is not drawn out in Sterling.

REGISTRATION will entitle you a copy of the most current version, minus the Registration messages, and a 50% discount on upgrades.

Please note that there is no printed manual.

### **On registration, you will also get;**

1. A copy of the most recent update of the program, licensed to you, and without all the registration messages.
2. Support for the program
3. A clear conscience
4. The satisfaction of being an honest person
5. Complimentary copies of some of my Windows utilities, namely;

[a] EXITWIN.EXE (click on the icon of this program, and you quit Windows - no fuss, no warnings, no questions)

[b] RUNWIN.EXE (click on the icon of this program, and Windows is shut down and restarted again - useful for those occasions when you need to reboot Windows, e.g. you have just installed a new device driver, or something has corrupted Windows, and you want to restart it).

[c] WINGREP.EXE (a Windows version of the popular GREP utility - to search for string patterns in ASCII files).

**If you wish to Register your copy, please send the payment to me at the address below, or to one of my registration sites;**

Dr. A. Olowofoyeku,  
268 Horwood,  
Newcastle,  
Staffordshire, ST5 5BQ  
ENGLAND.  
Internet:  
laa12@keele.ac.uk  
chief@mep.com

Please specify floppy disk size (3.5" or 5.25").

## **Registration Sites**

**YOU CAN SEND THE REGISTRATION FEE TO ANY OF THE FOLLOWING REGISTRATION SITES;**

### **CANADA, AND NORTH AMERICA**

Minds Edge Productions Inc.  
P. O. Box 211  
3456 Dunbar Street  
Vancouver, BC V6S 2C2  
Canada

Internet: [info@mep.com](mailto:info@mep.com)

Fidonet: 1:153/769

BBS: (604) 261-6144

Fee: \$26.00 (US funds)

or: \$30.00 (Canadian funds)

Method of payment: Checks, Money Orders

Make cheques/money orders payable to: "Minds Edge Productions Inc.".

British Columbia residents should add 7% sales Tax.

### **UNITED STATES**

TED KRAUS  
Synergy Online Communications Inc.  
P. O. Box 2630  
Mercerville  
NJ 08690  
U.S.A

Tel: (609) 587 6200

1-800-732 5856 (within the U.S.A only)

Internet: [ted.kraus@syncomm.com](mailto:ted.kraus@syncomm.com)

Fee: \$26.00 (US funds)

Method of payment: Checks, Money Orders, Visa, Mastercard, American Express.

Make cheques/money orders payable to: "TKO/ Real Estate Advisory Group Inc."

### **UNITED STATES**

TODD MERRIMAN  
Software Toolz, Inc.  
8030 Pooles Mill Dr.  
Ball Ground,  
GA 30107  
U.S.A.

Fax: 404-887-5960

Internet: software@toolz.atl.ga.us

Fee: \$26.00 (US funds)

Method of payment: Checks, Money Orders, Visa, Mastercard, American Express.

## **SCANDINAVIA AND NORTHERN EUROPE:**

HENRIK MOERK  
Survival BBS  
P.O.Box 1538  
DK-2700 Bronshoj  
Denmark

FIDO: 2:231/306

Internet: Lene@vax.psl.ku.dk  
Hmk@research.novo.dk

Kr170.00 (Danish funds)

Method of payment: Cheques, Eurocheques, Money Orders,

Make cheques/money orders payable to: "HENRIK MOERK".

## **AUSTRALIA, NEW ZEALAND, ASIA, AND THE FAR EAST**

DAVID PERKOVIC  
DP Computing  
P.O.Box 712  
Noarlunga Center  
SA 5168  
Australia

Internet: perkovic@cleese.apana.org.au  
dpc@mep.com

Tel: +61 8 326 4364

Fee: \$40.00 (Australian funds)

Method of payment: Cheques, Money Orders

Make cheques/money orders payable to: "DP Computing".

## **UNITED KINGDOM, IRELAND, EUROPE, AND EVERYWHERE ELSE**

Dr. A.A. OLOWOFOYEKU  
268 Horwood,  
Newcastle,  
Staffs, ST5 5BQ,  
ENGLAND.

Internet: laa12@keele.ac.uk  
chief@mep.com

Fee: £18.00 (U.K. funds; or equivalent)

plus: £3.00 (only if sending a foreign cheque)

Method of payment: Cheques, Eurocheques, Money Orders,

**To register WCL, please PRINT and FILL IN the following Registration FORM**

To:

---

---

---

---

I wish to REGISTER my copy of "WCL"

**I would like my registered copy sent to me by;**

**[a] 5.25" [     ] 3.5" [     ] Floppy Disk. (please tick)**

**OR**

**[b] by UUencoded e-mail [     ] (Internet addresses only)**

**(please note that the UUencoded ZIP file is about 380kb in size)**

I use the "big" [     ] "small" [     ] version (please tick)

I am paying the REGISTRATION FEE of \_\_\_\_\_

ADD Tax (if applicable) \_\_\_\_\_ (see the info on registration sites)

Total FEE: \_\_\_\_\_

I am paying by Cheque/Money Order/Credit Card (delete as inappropriate)

NAME \_\_\_\_\_

ADDRESS \_\_\_\_\_

---

---

POST/ZIP CODE \_\_\_\_\_

E-MAIL \_\_\_\_\_

How did you get your copy of WCL?

---

**IF PAYING BY CREDIT CARD, PLEASE SEND THE FOLLOWING DETAILS;**

**(NOTE: Not all sites accept credit cards so please refer to the list of REGISTRATION SITES)**

CARD ISSUER \_\_\_\_\_

CARD NUMBER \_\_\_\_\_

DATE OF ISSUE \_\_\_\_\_

EXPIRY DATE \_\_\_\_\_

SIGNATURE \_\_\_\_\_

DATE \_\_\_\_\_



