

button_gc

COLLABORATORS

	<i>TITLE :</i> button_gc		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		July 19, 2024	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	button_gc	1
1.1	button_gc.doc	1
1.2	button.gadget/--datasheet--	1
1.3	button.gadget/GM_GOACTIVE	3
1.4	button.gadget/GM_GOINACTIVE	4
1.5	button.gadget/GM_HANDLEINPUT	4
1.6	button.gadget/GM_HITTEST	4
1.7	button.gadget/GM_LAYOUT	5
1.8	button.gadget/GM_RENDER	5
1.9	button.gadget/OM_NEW	6
1.10	button.gadget/OM_SET	7

Chapter 1

button_gc

1.1 button_gc.doc

```
--datasheet--
GM_GOACTIVE
GM_GOINACTIVE
GM_HANDLEINPUT
GM_HITTEST
GM_LAYOUT
GM_RENDER
OM_NEW
OM_SET
```

1.2 button.gadget/--datasheet--

```
NAME
    button.gadget--Action button (V42)

SUPERCLASS
    gadgetclass

DESCRIPTION
    The button gadget class is used to create action buttons that are
    momentary, toggle and sticky. This class also supports relativity
    and placement within the window border.

    An advantage that this class provides that the system buttongclass
    doesn't support fully is:

    o Centered images.

    o Centered pen-sensitive glyphs.

    o Ability to change the text and background colors for normal
      and selected buttons.

METHODS
    OM_NEW--Create the button gadget. Passed to superclass, then OM_SET.
```

OM_SET--Set object attributes. Passed to superclass first.

OM_UPDATE--Set object notification attributes. Passed to superclass first.

GM_LAYOUT--Calculate gadget imagery positioning. Passed to superclass first.

GM_RENDER--Renders the gadget imagery. Overrides the superclass.

GM_HITTEST--Determines if mouse is within the gadget rectangle. Overrides the superclass.

GM_GOACTIVE--Handles activation, toggle-select and button-select. Overrides the superclass.

GM_HANDLEINPUT--Handles input events once active. Handles cycle buttons, repeat and RMB abort. Overrides the superclass.

GM_GOINACTIVE--Deselects the button. Overrides the superclass.

All other methods are passed to the superclass, including OM_DISPOSE.

ATTRIBUTES

GA_ToggleSelect (BOOL) -- Indicate that the gadget is a toggle button. Defaults to FALSE.

GA_Selected (BOOL) -- Determines whether the button is selected or not. Changing selection state will invoke GM_RENDER. Setting selected causes BUTTON_Current to go to 1. Clearing selected causes BUTTON_Current to go to 0. Defaults to FALSE.

GA_Disabled (BOOL) -- Determines whether the button is disabled or not. Changing disable state will invoke GM_RENDER. A disabled button's border and label are all rendered in SHADOWPEN and then dusted in a ghosting pattern that is rendered in SHADOWPEN. Defaults to FALSE.

GA_Text (STRPTR) -- Used to specify the NULL terminated string to use as the text for the gadget. The Text() function is used to draw the text. The class does not currently support underlining of the keyboard shortcut character. NULL is valid input. Changing the label will invoke GM_LAYOUT and then GM_RENDER.

GA_Image (struct Image *) -- Used to specify the image to use for the label of the gadget. The DrawImage() function is used to draw the image. NULL is valid input. Changing the label will invoke GM_LAYOUT and then GM_RENDER.

GA_TextAttr (struct TextAttr *) -- Text attribute for the font to use for the labels.

GA_ReadOnly (BOOL) -- Read-only gadgets ignore activation attempts. Defaults to FALSE.

BUTTON_Glyph (struct Image *) -- Used to specify the image to use for

the label of the gadget. The `BltTemplate()` function is used to draw each plane of the image. `NULL` is valid input. Changing the label will invoke `GM_LAYOUT` and then `GM_RENDER`.

`BUTTON_PushButton (BOOL)` -- Used to indicate that the button stays pressed in when the user selects it with the mouse. The button may programmatically be deselected using `{GA_Selected, FALSE}`. Defaults to `FALSE`.

`BUTTON_Array (LONG)` -- Indicates that the label is an array, and indicates the number of elements in the array. This allows the gadget to be used as a checkbox or a cycle gadget without the cycle glyph. Defaults to 1.

`BUTTON_Current (LONG)` -- Used to select the current image from the `BUTTON_Array`. Changing the current image will invoke `GM_LAYOUT` and then `GM_RENDER`. Defaults to zero.

`BUTTON_TextPen (LONG)` -- Indicate the pen number used to render the `IDS_NORMAL` text. If -1 is specified, then `TEXTPEN` is used. Defaults to -1.

`BUTTON_BackgroundPen (LONG)` -- Indicate the pen number used to render the `IDS_NORMAL` background. If -1 is specified, then `BACKGROUNDPEN` is used. Defaults to -1.

`BUTTON_FillTextPen (LONG)` -- Indicate the pen number used to render the `IDS_SELECTED` text. If -1 is specified, then `FILLTEXTPEN` is used. Defaults to -1.

`BUTTON_FillPen (LONG)` -- Indicate the pen number used to render the `IDS_SELECTED` background. If -1 is specified, then `FILLPEN` is used.
.
Defaults to -1.

1.3 button.gadget/GM_GOACTIVE

NAME

`GM_GOACTIVE`--Activate a gadget. (V42)

FUNCTION

The `GM_GOACTIVE` method is used to indicate to a gadget that it has become active. This method overrides the superclass.

`GA_ToggleSelect`: Toggles selection state.

`BUTTON_PushButton`: If not selected, then becomes selected and sets `BUTTON_Current` to 1. If selected and `BUTTON_Array` is greater than one, then will cycle through the array, while staying selected, with 1 being the lower bounds.

`BUTTON_Array`: Sets selection state and cycle through the array with 0 being the lower bounds.

Otherwise: Sets selection state.

Invokes GM_RENDER with GREDRAW_REDRAW set.

RESULT

For GA_ToggleSelect returns GMR_VERIFY | GMR_NOREUSE.

For BUTTON_PushButton returns GMR_VERIFY | GMR_NOREUSE when the state changes, otherwise returns GMR_NOREUSE.

All other cases returns GMR_MEACTIVE.

Sets the *msg->gpi_Termination field to BUTTON_Current, which in turn fills in the IntuiMessage->Code field.

1.4 button.gadget/GM_GOINACTIVE

NAME

GM_GOINACTIVE--Button has lost activation. (V42)

FUNCTION

The GM_GOINACTIVE method is used to indicate that the button has become inactive. This method overrides the superclass.

For momentary buttons, this will cause the GFLG_SELECTED flag to be cleared and the GM_RENDER method to be called with GREDRAW_REDRAW.

RESULT

This method returns 0.

1.5 button.gadget/GM_HANDLEINPUT

NAME

GM_HANDLEINPUT--Handle input events. (V42)

FUNCTION

The GM_HANDLEINPUT method is used to handle the input events of an active button gadget. This method overrides the superclass.

This method correctly handles RMB abort.

RESULT

This method returns GMR_MEACTIVE as long as the gadget is active.

1.6 button.gadget/GM_HITTEST

NAME

GM_HITTEST--Is gadget hit. (V42)

FUNCTION

The GM_HITTEST method is used to determine if the given mouse

coordinates are within the domain of the button. This method overrides the superclass.

RESULT

This method returns GMR_GADGETHIT if within the domain, otherwise zero is returned.

If the gadget is GA_ReadOnly, then zero is always returned.

1.7 button.gadget/GM_LAYOUT

NAME

GM_LAYOUT--Calculate the positioning of the imagery. (V42)

FUNCTION

The GM_LAYOUT method is used to calculate the domain of the button and to center the label within the domain. This method is passed to the superclass first.

Gadget relativity is fully supported.

RESULT

This method returns 0.

1.8 button.gadget/GM_RENDER

NAME

GM_RENDER--Render the visuals of the button. (V42)

FUNCTION

The GM_RENDER method is used to render the visuals of the button. This method overrides the superclass.

The border of the gadget is drawn first. Disabled gadgets get a border that is drawn completely in SHADOWPEN. A selected or read-only button gets SHADOWPEN for the left and top sides, and SHINEPEN for the right and bottom sides. A normal button gets SHINEPEN for the left and top sides, and SHADOWPEN for the right and bottom sides.

The inside of the button is then drawn. A normal button gets filled with BUTTON_BackgroundPen. A selected button gets filled with BUTTON_FillPen.

Then the label is drawn.

GA_Text: Text() is used to render the text. BUTTON_TextPen is used for a normal button and BUTTON_FillTextPen is used for a selected button.

GA_Image: DrawImageState() is used to render the image. Note that the background pen color is already set appropriately for

the image state.

BUTTON_Glyph: `BltTemplate()` is used to render each of the planes of the image. `BUTTON_TextPen` is used for a normal button and `BUTTON_FillTextPen` is used for a selected button. The second and higher planes are render using `SHADOWPEN`.

If the button is disabled, then the ghosting pattern is applied.

RESULT

This method returns 0.

1.9 button.gadget/OM_NEW

NAME

`OM_NEW`--Create a `button.gadget` object. (V42)

FUNCTION

The `OM_NEW` method is used to create an instance of the `button.gadget` class. This method is passed to the superclass first.

ATTRIBUTES

The following attributes can be specified at creation time.

`GA_ToggleSelect` (BOOL) -- Indicate that the gadget is a toggle button. Defaults to FALSE.

`GA_Selected` (BOOL) -- Determines whether the button is selected or not. Defaults to FALSE.

`GA_Disabled` (BOOL) -- Determines whether the button is disabled or not. Defaults to FALSE.

`GA_Text` (STRPTR) -- Used to specify the NULL terminated string to use as the text for the gadget.

`GA_Image` (struct Image *) -- Used to specify the image to use for the label of the gadget.

`GA_TextAttr` (struct TextAttr *) -- Text attribute for the font to use for the labels.

`GA_ReadOnly` (BOOL) -- Read-only gadgets ignore activation attempts. Defaults to FALSE.

`BUTTON_Glyph` (struct Image *) -- Used to specify the image to use for the label of the gadget.

`BUTTON_PushButton` (BOOL) -- Used to indicate that the button stays pressed in when the user selects it with the mouse. The button may programmatically be deselected using `{GA_Selected, FALSE}`. Defaults to FALSE.

`BUTTON_Array` (LONG) -- Indicates that the label is an array, and indicates the number of elements in the array. This allows the

gadget to be used as a checkbox or a cycle gadget without the cycle glyph. Defaults to 1.

`BUTTON_Current` (LONG) -- Used to select the current image from the `BUTTON_Array`. Defaults to zero.

`BUTTON_TextPen` (LONG) -- Indicate the pen number used to render the `IDS_NORMAL` text. If -1 is specified, then `TEXTPEN` is used. Defaults to -1.

`BUTTON_BackgroundPen` (LONG) -- Indicate the pen number used to render the `IDS_NORMAL` background. If -1 is specified, then `BACKGROUNDPEN` is used. Defaults to -1.

`BUTTON_FillTextPen` (LONG) -- Indicate the pen number used to render the `IDS_SELECTED` text. If -1 is specified, then `FILLTEXTPEN` is used. Defaults to -1.

`BUTTON_FillPen` (LONG) -- Indicate the pen number used to render the `IDS_SELECTED` background. If -1 is specified, then `FILLPEN` is used.
 . Defaults to -1.

RESULT

If the object was created then a pointer to the object is returned, otherwise `NULL` is returned.

1.10 button.gadget/OM_SET

NAME

`OM_SET`--Set the attributes of a `button.gadget` object. (V42)

FUNCTION

The `OM_SET` method is used to set the attributes of a `button.gadget`. This method is passed to the superclass first.

ATTRIBUTES

The following attributes can be changed at `OM_SET` or `OM_UPDATE`.

`GA_Selected` (BOOL) -- Determines whether the button is selected or not. Changing selection state will invoke `GM_RENDER`. Setting selected causes `BUTTON_Current` to go to 1. Clearing selected causes `BUTTON_Current` to go to 0. Defaults to `FALSE`.

`GA_Disabled` (BOOL) -- Determines whether the button is disabled or not. Changing disable state will invoke `GM_RENDER`. A disabled button's border and label are all rendered in `SHADOWPEN` and then dusted in a ghosting pattern that is rendered in `SHADOWPEN`. Defaults to `FALSE`.

`GA_Text` (STRPTR) -- Used to specify the `NULL` terminated string to use as the text for the gadget. The `Text()` function is used to draw the text. The class does not currently support underlining of the keyboard shortcut character. `NULL` is valid input. Changing the label will invoke `GM_LAYOUT` and then `GM_RENDER`.

GA_Image (struct Image *) -- Used to specify the image to use for the label of the gadget. The DrawImage() function is used to draw the image. NULL is valid input. Changing the label will invoke GM_LAYOUT and then GM_RENDER.

GA_TextAttr (struct TextAttr *) -- Text attribute for the font to use for the labels.

GA_ReadOnly (BOOL) -- Read-only gadgets ignore activation attempts. Defaults to FALSE.

BUTTON_Glyph (struct Image *) -- Used to specify the image to use for the label of the gadget. The BltTemplate() function is used to draw each plane of the image. NULL is valid input. Changing the label will invoke GM_LAYOUT and then GM_RENDER.

BUTTON_Current (LONG) -- Used to select the current image from the BUTTON_Array. Changing the current image will invoke GM_LAYOUT and then GM_RENDER. Defaults to zero.

BUTTON_TextPen (LONG) -- Indicate the pen number used to render the IDS_NORMAL text. If -1 is specified, then TEXTPEN is used. Defaults to -1. Changing the pen will invoke GM_RENDER.

BUTTON_BackgroundPen (LONG) -- Indicate the pen number used to render the IDS_NORMAL background. If -1 is specified, then BACKGROUNDPEN is used. Defaults to -1. Changing the pen will invoke GM_RENDER.

BUTTON_FillTextPen (LONG) -- Indicate the pen number used to render the IDS_SELECTED text. If -1 is specified, then FILLTEXTPEN is used. Defaults to -1. Changing the pen will invoke GM_RENDER.

BUTTON_FillPen (LONG) -- Indicate the pen number used to render the IDS_SELECTED background. If -1 is specified, then FILLPEN is used . Defaults to -1. Changing the pen will invoke GM_RENDER.

RESULT

The class will update the attributes of object. Changing some attributes will result in GM_LAYOUT and/or GM_RENDER being called.

The return value will be non-zero if the gadget needs to be refreshed.
