

# README File for CompuServe 3.0.4

July 1997

This README File contains installation procedures, feature highlights, and other information to get you started using CompuServe. If you have already installed CompuServe, please skip System Requirements and Installation Notes, and continue with the sections that follow.

## Contents

1. Upgrading to CompuServe 3.0.4
2. System Requirements
3. Installation Notes
  - 3.1 Installing CompuServe for Windows 95 and Windows NT 4.0
  - 3.2 Installing CompuServe for Windows NT 3.51
4. Connectivity with CompuServe
  - 4.1 Dial-Up Networking in CompuServe for Windows 95
  - 4.2 Configuring the Windows NT 3.5.1 Dial-Up Remote Access Service (RAS Dialer)
  - 4.3 Configuring the Windows NT 4.0 Dial-Up Remote Access Service (RAS Dialer)
  - 4.4 Signup or Startup?
5. Upgrading Your Filing Cabinet
  - 5.1 Filing Cabinet Conversion
  - 5.2 Filing Cabinet Utility
6. Setting Up Netscape Navigator as Your External Web Browser
7. Feature Highlights of CompuServe
8. Support Information
  - 8.1 Help System
  - 8.2 Online Resources
9. Recovering Hard Disk Space
10. Proxy Servers and Firewalls

## 1. Upgrading to CompuServe 3.0.4

If you are running CompuServe 3.0.1 or CompuServe 3.0.2, we recommend you upgrade to CompuServe 3.0.4. CompuServe 3.0.4 incorporates the latest bug fixes and mail speed improvements, provides better connectivity, and offers context-sensitive help.

## 2. System Requirements

### Windows 95

- 8 Mb RAM (16 recommended)
- 60 Mb free hard disk (to install)\*
- 28 Mb free hard disk (to run)
- 486 33 or better processor
- VGA Monitor (640x480)
- 9600 baud (or higher) connection rate

### Windows NT 3.51 and NT 4.0

- 16 Mb RAM
- 60 Mb free hard disk (to install)\*
- 28 Mb free hard disk (to run)
- 486 33 or better
- VGA Monitor (640x480)
- 9600 baud (or higher) connection rate

\* If you encounter errors during installation, increasing the free hard disk space to 70 or 80 Mb may resolve them.

## 3. Installation Notes

CompuServe 3.0.4 can coexist with the CompuServe Information Manager for Windows (WinCIM) and the CompuServe 2.x series and will share common files (like CompuServe Mail's

Address Book). CompuServe 3.0.4 is installed in a separate folder and will not overwrite earlier versions of CompuServe 3.0.x.

It is recommended that you install CompuServe 3.0.4 in the same directory as your other CompuServe programs. By doing so, CompuServe 3.0.4 will automatically have access to your current information, such as settings, Address Book listings, quotes, portfolio entries, your Favorite Places, and other information.

### **3.1 Installing CompuServe for Windows 95 and NT 4.0:**

1. Insert CD-ROM in drive.
2. Click on Start Menu and choose Run.
3. Type D:\RUN.EXE and then click OK. (Replace D: with your drive letter if different.)

Note: If you have the Windows 95 CD AutoPlay feature enabled, the program will start automatically after you place the CD in the appropriate drive.

### **3.2 Installing CompuServe for Windows NT 3.51:**

1. Insert CD-ROM in drive.
2. From the Program Manager, choose File and then Run.
3. Type D:\RUN.EXE and then click OK. (Replace D: with your drive letter if different.)
4. If you do not have TCP/IP connectivity already installed and configured, follow the instructions under "Configuring the Windows NT 3.5.1 Dial-Up Remote Access Service (RAS Dialer)" in the next section.

## **4. Connectivity with CompuServe**

### **4.1 Dial-Up Networking in CompuServe for Windows 95**

The Windows 95 version of CompuServe automatically utilizes Microsoft's Dial-Up Networking capability.

This section explains three scenarios:

1. You have no pre-existing CompuServe software on your computer and are installing CompuServe for the first time.

*Note: This scenario also applies if you are replacing an earlier version of CompuServe 3.0.x with CompuServe 3.0.4.*

Recommended Installation Method: Express

2. You are a current member and you have previous CompuServe software on your machine and you are installing CompuServe for the first time into the same directory as your pre-existing CompuServe software.

Recommended Installation Method: Express

3. You have a pre-existing Winsock, such as Trumpet or LAN connection, installed and are installing CompuServe for the first time.

Recommended Installation Method: Custom Install

**Scenario #1: Installing CompuServe for the First Time (or as an upgrade to an earlier version of 3.0.x)**

**Express Installation:** When you choose Express installation, CompuServe automatically sets up Microsoft's Dial-Up Networking by default. When installed through the Express method, CompuServe also uses Microsoft's WSOCK32.DLL file.

After Express installation, your Connection Preferences will be set for Dial-Up Networking in the Winsock Connection Type pop-up menu and CS3 Connection in the Connect Using pop-up menu.

**Custom Installation:** Custom installation of CompuServe gives you a choice for connectivity. You can either choose **Install Dial-Up Networking** or **Use Existing Internet Connectivity**, if you don't want to use Dial-Up Networking.

If you select Install Dial-Up Networking, CompuServe will use Dial-Up Networking to connect to CompuServe. Your Connection Preferences will be set for **Dial-Up Networking** in the Winsock Connection Type pop-up menu and **CS3 Connection** in the Connect Using pop-up menu - just like the Express installation.

If you select **Use Existing Internet Connectivity**, CompuServe will not install Dial-Up Networking and will instead use the first 32-bit Winsock it finds. The Connection Preferences will be set for **Default Winsock** in the Winsock Connection Type pop-up menu and the Dial-Up Networking box will be grayed out.

#### **Scenario #2: Installing CompuServe into the same directory as WinCIM 2.x**

When you upgrade from WinCIM 2.0.1 and install CompuServe into the same directory (usually /CSERVE), CompuServe behaves exactly as it would if you had installed it for the first time. Dial-Up Networking is installed by default when Express Installation is used and you can avoid installing Dial-Up Networking by using the Custom Installation and selecting Use Existing Internet Connectivity.

Installing CompuServe into the same directory as WinCIM 2.x will not affect WinCIM's connection process.

#### **Scenario #3: Installing CompuServe with a Pre-Existing Winsock**

If you have a pre-existing Winsock, you will need to install using the Custom method and should select **Use Existing Internet Connectivity** when asked. Otherwise, Microsoft's install of Dial-Up Networking may overwrite your pre-existing Winsock.

#### **Dial-Up Networking Phone Settings**

For those of you who choose to install Dial-Up Networking, CompuServe creates a Dial-Up Networking connection, named "CS3 Connection," which contains the phone number to be used to connect to the CompuServe network.

To modify your phone settings using Dial-Up Networking after installation, select Preferences from the Access menu. Then, at the Connection page, enter the phone number to dial when connecting to CompuServe in the Phone # box.

#### **4.2 Configuring the Windows NT 3.5.1 Dial-Up Remote Access Service (RAS Dialer):**

Unless otherwise noted all settings or selections not specifically mentioned should be left at their default entries.

***Assuming you have not previously added RAS:***

1. In the Control Panel, double-click the Network icon.
2. In the Network Settings window, click the Add Software button.
3. From the pop-up list in the Network Software window, select Remote Access Service.
4. Provide a path to your NT distribution (disks, CD, or network location).

RAS will then install, and the Remote Access Program Group will appear.

5. In the Add Port window, select the port you will use.

RAS will offer to detect the modem connected to the port you selected. Choose OK to auto-detect the modem. NT will show the modem detected. Select OK.

Occasionally, NT may offer a choice of several modems to pick from. This will only occur if RAS cannot distinguish between 2 or more modems with similar characteristics.

6. In the Configure Port window, the detected modem will be highlighted. In the Port Usage section, choose "Dial out only."

RAS is now installed. The next step is to configure it to dial CompuServe.

### ***Editing SWITCH.INF***

1. Using a text editor such as Notepad or Edit, add the following section to the bottom of your SWITCH.INF file (normally located at WINNT\system32\ras\switch.inf):

=====

```
[CompuServe]
COMMAND=<cr>
OK=<match>"e:"
ERROR_NO_CARRIER=<match>"NO CARRIER"
LOOP=<ignore>
COMMAND=+<cr>
OK=<match>"Host Name"
ERROR_NO_CARRIER=<match>"NO CARRIER"
LOOP=<ignore>
COMMAND=CIS<cr>
OK=<match>"User ID:"
ERROR_NO_CARRIER=<match>"NO CARRIER"
LOOP=<ignore>
COMMAND=#####,#####GO:PPPCONNECT<cr>
OK=<match>". "
ERROR_NO_CARRIER=<match>"NO CARRIER"
LOOP=<ignore>
COMMAND=PASSWORD<cr>
CONNECT=<ignore>
```

2. Be sure to put in your actual CompuServe User ID [123456,1234] and CompuServe password [XXXX0XXXXX] in place of #####,##### and PASSWORD.
3. Save the file.

### ***Editing the RAS phonebook***

1. Go to the Remote Access Program Group and double-click the Remote Access icon. In the

resulting window, click Add.

You will be presented with an Add Phone Book Entry window.

2. Name the new entry "CompuServe" or whatever you want.
3. Enter the phone number of your local CompuServe dial-up site. Be sure to include any special characters needed, such as 9 to reach an outside line or \*70 to disable call waiting.
4. Leave the Description field blank (optional).
5. Make sure that "Authenticate using current name and password" is not marked.
6. Select the correct COM port for your modem.
7. Click the Modem button and choose the correct port speed. Mark "Enable hardware flow control," "Enable modem error control," and "Enable modem compression." Do not mark "Enter modem commands manually." Click OK.
8. Select the Network option. Choose PPP and mark "TCP/IP" and "Request LCP extension."
9. Click the "TCP/IP Settings" button. Choose "Server Assigned IP address" and "Use specific name server addresses." Then enter in DNS 149.174.211.5 and DNS Backup 149.174.213.5. Mark both "Use VJ header compression" and "Use default gateway on remote host."
10. Select the Security option.

Make sure "Accept any authentication including clear text" is selected.

In the "Terminal or Script" section, select CompuServe in the pop-up menu for "After Dialing." (The CompuServe option will only be available if you made the necessary changes to SWITCH.INF.) Then Click OK.

Return to the Remote Access window. You will now see a new setting for CompuServe. Simply select Dial to connect to CompuServe.

#### **4.3 Configuring the Windows NT 4.0 Dial-Up Remote Access Service (RAS Dialer)**

Unless otherwise noted all settings or selections not specifically mentioned should be left at their default entries.

##### ***Installing RAS/DUN in Windows NT 4.0***

1. Double-click on the My Computer icon and then double-click on the Dial-up Networking icon.

If RAS/DUN is not installed, you will see the Welcome to Dial-Up Networking window.

2. Click the Next button to begin.

The DUN installation will ask for the Windows NT 4.0 CD-ROM and then install the DUN/RAS files from it.

Note: You must have Administrator privileges to install RAS. TCP/IP and other necessary components should be installed along with RAS; if they are not installed correctly, consult your manual or VAR.

3. In the Add RAS Device window, choose the modem to use with RAS/DUN and then click OK.

If no modem is installed choose Install Modem; after installing the modem, click OK.

4. In the Remote Access Setup window, select the Configure button.
5. In the Configure Port Usage window, choose "Dial out only" and then click OK.
6. In the Remote Access Setup window, select the Network button.

In the Network Configuration window, be sure that only TCP/IP is marked and click OK. Some additional files may be installed from the Windows NT 4.0 CD-ROM.

If there is a network interface card installed that does not already have TCP/IP bound to it, the Microsoft TCP/IP Properties window will appear. Click Cancel to close the window.

If there is a network card, you will see a warning that TCP/IP is not completely configured. This warning refers to TCP/IP over the network and should not be set up. Select Yes.

7. Select Restart to complete the RAS/DUN installation.

### ***Creating and Setting Up the Connection Entry***

1. Double-click on the My Computer icon, then double-click on the Dial-up Networking icon.

Note: If you are notified that RAS/DUN is not installed, refer to the steps in the previous section, Installing RAS/DUN in Windows NT 4.0.

2. In the Dial-Up Networking window, select the New button.

3. In the New Phonebook Entry Wizard window, enter CompuServe for the name and select the Next button.

4. In the Server window mark the "I am calling the Internet" and "Send my password as plain text if that's the only way to connect" boxes and select the Next button.

5. In the Phone Number window, enter your local CompuServe Access phone number and select the Next button. Enter any Alternate numbers by choosing Alternate.

6. In the New Phonebook Entry Wizard select the Finish button

Note: If this is the first time you have made a Dial-Up Networking entry, you will have a few more screens; just click on the Next button for each one.

7. In the Dial-up Networking window select the More button, then select "Edit entry" and "modem properties." You can also select "Create shortcut to entry" on this menu to place a shortcut icon on your desktop.

8. The "Edit Phonebook Entry, Basic" tab lists basic information about the entry. You can also select the Alternates button to enter alternate phone numbers to dial. Selecting the Configure button will allow you to set some modem properties.

9. After clicking the Alternates button, you can enter additional phone numbers to dial.

10. After clicking the Configure button, you can edit some of the modem properties.

11. Click on the Server tab and mark only TCP/IP; unmark all other boxes. (Software compression can also be marked but, in rare instances, this may cause problems.)

12. On the Server tab, select the TCP/IP Settings button. In the PPP TCP/IP Settings window, set IP Address for "Server assigned." Then set the DNS for "Server Assigned" also. Leave Wins all zeros, mark both boxes at the bottom and then click OK.

13. Click on the the Script tab and, from the pop-up list, select cis.scp. You may also want to edit the script and change the "/go:pppconnect^m" to "/noint/go:pppconnect^m" to speed up the logon.

14. Select the Before Dialing button and make sure that "None" is marked, then click OK.

15. Click on the Security tab and mark "Use any authentication including clear text." This is also where The Unsave password button will unsave your password so that you can re-enter it, if necessary (see step 22).

16. Settings on the X.25 tab should be blank. Then click OK.

17. For additional settings, click the More button, then select User Preferences from the menu.

18. On the Dialing tab you can set the number of retries and whether or not DUN redials if the connection is lost. Set Idle seconds before hangup so that Dial-Up Networking disconnects, if left idle. Also make sure the box next to the current location is marked in the Autodial by location box.

19. On the Callback tab mark "No, skip callback".
20. On the Appearance tab there are various options. These should be left at their default settings.
21. On the Phonebook tab mark "The System Phonebook."
22. Select Dial in the Dial-up Networking window. In the Connect to CompuServe window enter your CompuServe User ID number (with the comma) in the User Name field and your password in the Password field. Leave the Domain field empty and mark Save password if you want to save your password. If you need to change your password, you also would need to click the Unsave password button on the Security tab (step 15).
23. Click on OK to dial. Do not disturb the After Dial Terminal window, but watch the login and if you see the message "?? LOGINE - Invalid entry - try again" after the Password: prompt, your password is incorrect.
24. In the SysTray on the Taskbar, there will be the Dial-Up Network icon. If you right-click on this icon, you can hang up the connection or select Open Dial-up Monitor to get information about your connection, including the DCE connection speed(bps) and your IP address (Details button).

### ***Making RAS Autodial***

If you are not using TCP/IP on your Ethernet card, follow these steps to make RAS autodial:

1. Go to the Control Panel and double-click on the Network icon; then click on the Bindings Tab.
2. In the "Show bindings for" drop-down list, select "All Protocols."
3. Click on the plus sign next to TCP/IP and WINS Client(TCP/IP).
4. Select the Ethernet card on both the TCP/IP and WINS Client; then click the Disable button.
5. Click OK. Then click Yes in the Network Setting Change window to restart your computer.
6. In the Control Panel, double-click on Services.
7. In the Service Control Panel, make sure that "Remote Access Autodial Manager" is started and set to Automatic. (It should be set to Automatic by default. If it is not, click Startup and then change the Startup Type to Automatic.)

After you've completed these steps, RAS will autodial the connection whenever you start a Winsock application.

### ***Interpreting Error Messages: "Could not resolve Gateway.compuserve.com" or "Winsock Error: Host not found"***

There are two basic reasons these error messages occur.

1. The modem did not dial/connect and therefore it cannot get to the DNS servers or the CompuServe host.

Suggested solution: Try starting the connection first.

2. A problem has occurred with the DNS entries in the Network Control panel.

Suggested solution: If you are not running TCP/IP on your network, disable TCP/IP on the ethernet card as described in the previous section, Making RAS Autodial.

If you are running TCP/IP on your network, go to the Control Panel, then double-click on the Network icon. In the Network control panel, click the Protocols tab, double-click on TCP/IP, and then click the DNS tab. To solve the problem, you will need to add one of the CompuServe DNS servers (149.174.213.5 or 149.174.211.5) to the list in the DNS window.

## **4.4 Signup or Startup?**

Based on whether it finds a CIS.INI file or not, CompuServe can usually determine your

membership status and will prompt you to sign up a new account or set up the software (if you are an existing member).

If a CIS.INI file is not detected, you will see the Welcome window, where you can either sign up a new account or set up the software. New members should always select Signup from the Welcome window. Be sure to exit all applications, including screen savers and toolbars, before starting the signup process.

However, if you already have a CompuServe account and are running from a directory where CIS.INI cannot be found, you will need to select Setup.

Current members should note that CompuServe 3.0.4 does not include a Winsock checkbox in the Connection settings, as the WinCIM 2.x series does. All CompuServe 3.0.4 connections require PPP and use Winsock. This feature enables us to provide easy Internet access and new built-in multi-tasking support.

## **5. Upgrading Your Filing Cabinet**

The CompuServe Filing Cabinet stores Mail messages, Forum messages, news articles (stories), and other types of text articles that you want to review or use later. Simply click the File It button in the message or article window, and then select or create the folder in which you want to store it.

To access the Filing Cabinet, click the My Information side button (on the Home Desktop), and then click the Filing Cabinet top tab. Or, select the Filing Cabinet button located on the toolbar.

### **5.1 Filing Cabinet Conversion**

The Filing Cabinet in CompuServe 3.0.4 uses a different format than the Filing Cabinets in CompuServe software prior to CompuServe 3. Items stored in the WinCIM Filing Cabinet must be converted before you can view them in CompuServe 3.0.4. However, you can view Filing Cabinet items stored in more recent versions of CompuServe's software (CompuServe 3.0 and later) with CompuServe 3.0.4.

If you install CompuServe (3.0 and later versions) into the same directory as your other CompuServe products, items in your WinCIM Filing Cabinet are converted automatically the first time you use CompuServe.

#### **Filing Cabinet Conversion Utility**

This utility converts the contents of a Filing Cabinet created with versions of WinCIM, DOSCIM, and CSNav to the new CompuServe 3 format. Although it runs automatically the first time you install CompuServe 3.0.4, it can be run any time.

To convert the contents of the Filing Cabinet after the initial installation of CompuServe:

1. Start the Filing Cabinet Conversion Utility (located in the CompuServe program group).
2. Type the source and destination directory paths in the Convert Filing Cabinet window.
3. Click Begin.

### **5.2 Filing Cabinet Utility**

This utility enables you to perform backup and general maintenance on your Filing Cabinet. In addition to backup, you can use it to recover wasted space, repair damaged records, and merge information from multiple Filing Cabinets. Features include:

- Backup



- Restore
- Compress
- Repair
- Statistics
- Preferences

To back up (copy) your Filing Cabinet:

1. Start the Filing Cabinet Backup Utility (located in the CompuServe program group).
2. Choose the Copy to file command from the File menu.

A window will be displayed where you can specify the current Filing Cabinet directory and the name of the file (backup file) you want to create.

General maintenance tasks can be performed using appropriate commands on the Filing Cabinet menu.

## **6. Setting Up Netscape Navigator as Your External Web Browser**

These instructions apply to Netscape Navigator 2.0.2 and higher.

In CompuServe:

1. Select Preferences from the Access menu.
2. Click on the General top tab.
3. Click the Select button.
4. Find NETSCAPE.EXE and double-click it.
5. On the General top tab, mark the "Use external Internet browser" checkbox and click OK.

In Netscape Navigator:

1. Choose General Preferences from the Options menu.
2. Click on the Helpers top tab.
3. Click the Create New Type button.
4. In the Mime Type field, enter "application" (no quotes).
5. In the Mime sub-type field, enter "x-gocserve" (no quotes).
6. Click OK.
7. In the File Extension field on the Helper tab, enter "go" (no quotes).
8. Mark the "Launch the application" option.
9. Click the Browse button and double-click GOCSERVE.EXE. Then click OK.

## **7. Feature Highlights of CompuServe**

### **A New Multimedia Look**

CompuServe has a redesigned, multimedia interface that is graphically rich and easy to navigate. It also allows automatic viewing of files such as charts, photos, and other multimedia files.

### **New Web Browser for Windows 95 and Windows NT 4.0: Microsoft Internet Explorer 3.02**

We also offer complete, easy access to the Internet through our integrated Web browser from Microsoft, Internet Explorer 3.0.2.

CompuServe contains the latest version of Internet Explorer 3.0.2. If you have the same (or an older) version installed on your computer, then CompuServe will install the newest version to

ensure that you are running the latest software and that your current installation is complete. If you currently have a newer version than the one in CompuServe installed, CompuServe will use it.

For Windows NT 3.51 users, we offer Internet access with Microsoft Internet Explorer 2.1.

## **Multi-Tasking**

CompuServe has multi-tasking capability, which saves you time by allowing you to perform multiple tasks simultaneously. Use the To-Do List to manage retrieval of messages and files in the 'background,' while you are doing other online activities, such as reading news articles or browsing a Forum area in the 'foreground.'

## **Personalized, Customizable Features**

CompuServe provides time-saving, organizational tools that let you track where you've been by checking your list of recently visited places, save frequently-visited places in your Favorite Places list, or customize your toolbar for easy access to frequently-used tasks.

## **Free Software**

Look in your \BONUS\_W directory on your CD-ROM drive (D: in most cases) for free bonus software. Included on your CD are titles such as WorldsAway, Air Warrior II, BattleTech, Adobe Acrobat, Casino Poker, and more. Just install the software you're interested in and enjoy - compliments of CompuServe.

## **8. Support Information**

### **8.1 Help System**

**Learn About Help:** Most main desktops have a Learn About side button, which you can click to find out how to accomplish your tasks using the desktop features. If you're a new member, new to CompuServe 3.0.4, or not a frequent user, Learn About Help is a good place to begin.

**Help Menu:** To learn how to use the Help system, choose "How to Use Help" from the Help Menu. Choose "Contents" from the Help menu to view the Help system's table of contents.

### **8.2 Online Resources**

Once you have installed CompuServe and become a member, you can connect to CompuServe for a wealth of information, software, and services. Simply click the Assistance top tab on the Home Desktop, then click Member Services to view a menu of available resources for help and assistance. For information and support on CompuServe 3.0.4, type GO CSWIN to go directly to the support area for CompuServe software for Windows.

## **9. Recovering Hard Disk Space**

If you need additional space on your hard drive, here are some suggestions:

- Deleting old WinCIM Signup files will recover 600K. To do so, delete C:\CSERVE\WINSIGN.
- Deleting Mosaic cache files will recover up to 5 Mb (if you used the default cache size). To do so, delete C:\CSERVE\MOSAIC\CACHE.
- Deleting the Mosaic software will free up to 1.9 Mb. However, be aware that this will also remove any hotlists you have in Mosaic. To do so, delete C:\CSERVE\MOSAIC.

- If you no longer need to use WinCIM, you can recover approximately 2 Mb by deleting C:\CSERVE\WINCIM.

Caution: Do not delete the contents of your C:\CSERVE directory when you are deleting the sub-directories.

## **10. Proxy Servers and Firewalls**

In general, CompuServe 3.0.4 uses port 4144 to communicate to gateway.compuserve.com. Because there are so many different Proxy Server and Firewall setups, individual setups cannot be covered here. You'll need to contact your System Administrator about the proper setup.